D01 – Quadrature D01ATF

NAG Fortran Library Routine Document D01ATF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

D01ATF is a general-purpose integrator which calculates an approximation to the integral of a function f(x) over a finite interval [a, b]:

$$I = \int_a^b f(x) \, dx.$$

2 Specification

```
SUBROUTINE DO1ATF(F, A, B, EPSABS, EPSREL, RESULT, ABSERR, W, LW, IW, LIW, IFAIL)

INTEGER
LW, IW(LIW), LIW, IFAIL

real
A, B, EPSABS, EPSREL, RESULT, ABSERR, W(LW)

EXTERNAL
F
```

3 Description

D01ATF is based upon the QUADPACK routine QAGS (Piessens *et al.* (1983)). It is an adaptive routine, using the Gauss 10-point and Kronrod 21-point rules. The algorithm, described by de Doncker (1978), incorporates a global acceptance criterion (as defined by Malcolm and Simpson (1976)) together with the ϵ -algorithm (Wynn (1956)) to perform extrapolation. The local error estimation is described by Piessens *et al.* (1983).

The routine is suitable as a general purpose integrator, and can be used when the integrand has singularities, especially when these are of algebraic or logarithmic type.

The routine requires a user-supplied subroutine to evaluate the integrand at an array of different points and is therefore particularly efficient when the evaluation can be performed in vector mode on a vector-processing machine. Otherwise the algorithm is identical to that used by D01AJF.

4 References

de Doncker E (1978) An adaptive extrapolation algorithm for automatic integration *ACM SIGNUM Newsl.* **13 (2)** 12–18

Malcolm M A and Simpson R B (1976) Local versus global strategies for adaptive quadrature *ACM Trans. Math. Software* **1** 129–146

Piessens R, de Doncker-Kapenga E, Überhuber C and Kahaner D (1983) *QUADPACK, A Subroutine Package for Automatic Integration* Springer-Verlag

Wynn P (1956) On a device for computing the $e_m(S_n)$ transformation Math. Tables Aids Comput. 10 91–96

5 Parameters

1: F - SUBROUTINE, supplied by the user. External Procedure F must return the values of the integrand f at a set of points.

[NP3546/20A] D01ATF.1

Its specification is:

SUBROUTINE F(X, FV, N)

INTEGER 1

real X(N), FV(N)

1: X(N) - real array

Input

On entry: the points at which the integrand f must be evaluated.

2: FV(N) - real array

Output

On exit: FV(j) must contain the value of f at the point X(j), for j = 1, 2, ..., N.

3: N - INTEGER

Input

On entry: the number of points at which the integrand is to be evaluated. The actual value of N is always 21.

F must be declared as EXTERNAL in the (sub)program from which D01ATF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: A - real Input

On entry: the lower limit of integration, a.

3: B - real Input

On entry: the upper limit of integration, b. It is not necessary that a < b.

4: EPSABS – real Input

On entry: the absolute accuracy required. If EPSABS is negative, the absolute value is used. See Section 7.

5: EPSREL – *real* Input

On entry: the relative accuracy required. If EPSREL is negative, the absolute value is used. See Section 7.

6: RESULT – real Output

On exit: the approximation to the integral I.

7: ABSERR – real Output

On exit: an estimate of the modulus of the absolute error, which should be an upper bound for |I - RESULT|.

8: W(LW) - real array Output

On exit: details of the computation, as described in Section 8.

9: LW – INTEGER Input

On entry: the dimension of the array W as declared in the (sub)program from which D01ATF is called. The value of LW (together with that of LIW below) imposes a bound on the number of sub-intervals into which the interval of integration may be divided by the routine. The number of sub-intervals cannot exceed LW/4. The more difficult the integrand, the larger LW should be.

Suggested value: a value in the range of 800 to 2000 is adequate for most problems.

Constraint: LW \geq 4.

D01ATF.2 [NP3546/20A]

D01 – Quadrature D01ATF

10: IW(LIW) – INTEGER array

Output

On exit: IW(1) contains the actual number of sub-intervals used. The rest of the array is used as workspace.

11: LIW – INTEGER Input

On entry: the dimension of the array IW as declared in the (sub)program from which D01ATF is called. The number of sub-intervals into which the interval of integration may be divided cannot exceed LIW.

Suggested value: LIW = LW/4.

Constraint: LIW ≥ 1 .

12: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL $\neq 0$ on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

The maximum number of subdivisions allowed with the given workspace has been reached without the accuracy requirements being achieved. Look at the integrand in order to determine the integration difficulties. If the position of a local difficulty within the interval can be determined (e.g., a singularity of the integrand or its derivative, a peak, a discontinuity, etc.) you will probably gain from splitting up the interval at this point and calling the integrator on the subranges. If necessary, another integrator, which is designed for handling the type of difficulty involved, must be used. Alternatively, consider relaxing the accuracy requirements specified by EPSABS and EPSREL, or increasing the amount of workspace.

IFAIL = 2

Round-off error prevents the requested tolerance from being achieved. The error may be underestimated. Consider requesting less accuracy.

IFAIL = 3

Extremely bad local integrand behaviour causes a very strong subdivision around one (or more) points of the interval. The same advice applies as in the case of IFAIL = 1.

IFAIL = 4

The requested tolerance cannot be achieved, because the extrapolation does not increase the accuracy satisfactorily; the returned result is the best which can be obtained. The same advice applies as in the case of IFAIL = 1.

[NP3546/20A] D01ATF.3

IFAIL = 5

The integral is probably divergent, or slowly convergent. Please note that divergence can occur with any non-zero value of IFAIL.

IFAIL = 6

On entry,
$$LW < 4$$
, or $LIW < 1$.

7 Accuracy

The routine cannot guarantee, but in practice usually achieves, the following accuracy:

$$|I - RESULT| \le tol$$

where

$$tol = \max\{|\text{EPSABS}|, |\text{EPSREL}| \times |I|\}$$

and EPSABS and EPSREL are user-specified absolute and relative error tolerance. Moreover, it returns the quantity ABSERR which, in normal circumstances, satisfies

$$|I - \mathsf{RESULT}| \leq \mathsf{ABSERR} \leq tol.$$

8 Further Comments

If IFAIL $\neq 0$ on exit, then the user may wish to examine the contents of the array W, which contains the end-points of the sub-intervals used by D01ATF along with the integral contributions and error estimates over the sub-intervals.

Specifically, for i = 1, 2, ..., n, let r_i denote the approximation to the value of the integral over the sub-interval $[a_i, b_i]$, in the partition of [a, b], and e_i be the corresponding absolute error estimate.

Then, $\int_{a_i}^{b_i} f(x) \, dx \simeq r_i$ and RESULT = $\sum_{i=1}^n r_i$, unless D01ATF terminates while testing for divergence of the integral (see Section 3.4.3 of Piessens *et al.* (1983)). In this case, RESULT (and ABSERR) are taken to be the values returned from the extrapolation process. The value of n is returned in IW(1), and the values of a_i , b_i , e_i and r_i are stored consecutively in the array W, that is:

$$\begin{array}{rcl} a_i & = & \mathrm{W}(i), \\ b_i & = & \mathrm{W}(n+i), \\ e_i & = & \mathrm{W}(2n+i) \text{ and } \\ r_i & = & \mathrm{W}(3n+i). \end{array}$$

9 Example

To compute

$$\int_0^{2\pi} \frac{x \sin(30x)}{\sqrt{1 - (x/2\pi)^2}} \, dx.$$

D01ATF.4 [NP3546/20A]

D01 – Quadrature D01ATF

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
D01ATF Example Program Text
      Mark 17 Revised. NAG Copyright 1995.
      .. Parameters ..
                       NOUT
      INTEGER
      PARAMETER
                       (NOUT=6)
      INTEGER
                       LW, LIW
      PARAMETER
                       (LW = 800, LIW = LW/4)
      .. Scalars in Common ..
      real
                       PΤ
      INTEGER
                       KOUNT
      .. Local Scalars ..
                       A, ABSERR, B, EPSABS, EPSREL, RESULT
      INTEGER
                       IFAIL
      .. Local Arrays ..
      real
                       W(LW)
      INTEGER
                       IW(LIW)
      .. External Functions ..
      real
                       X01AAF
      EXTERNAL
                       X01AAF
      .. External Subroutines .. EXTERNAL DOIATF, FST
      EXTERNAL
      .. Common blocks ..
                       /TELNUM/PI, KOUNT
      COMMON
      .. Executable Statements ..
      WRITE (NOUT,*) 'D01ATF Example Program Results'
      PI = X01AAF(0.0e0)
      EPSABS = 0.0e0
      EPSREL = 1.0e-04
      A = 0.0e0
      B = 2.0e0*PI
      KOUNT = 0
      IFAIL = -1
      CALL DO1ATF(FST,A,B,EPSABS,EPSREL,RESULT,ABSERR,W,LW,IW,LIW,IFAIL)
      WRITE (NOUT, *)
      WRITE (NOUT, 99999) 'A
                                  - lower limit of integration = ', A
      WRITE (NOUT, 99999) 'B
                                  - upper limit of integration = '
      WRITE (NOUT, 99998) 'EPSABS - absolute accuracy requested = ',
       EPSABS
      WRITE (NOUT, 99998) 'EPSREL - relative accuracy requested = ',
     + EPSREL
      WRITE (NOUT, *)
      IF (IFAIL.NE.O) WRITE (NOUT, 99996) 'IFAIL = ', IFAIL
      IF (IFAIL.LE.5) THEN
         WRITE (NOUT,99997) 'RESULT - approximation to the integral = ',
           RESULT
         WRITE (NOUT,99998) 'ABSERR - estimate of the absolute error = '
           , ABSERR
         WRITE (NOUT, 99996)
           'KOUNT - number of function evaluations = ', KOUNT
         WRITE (NOUT, 99996) 'IW(1) - number of subintervals used = ',
           IW(1)
      END IF
      STOP
99999 FORMAT (1X,A,F10.4)
99998 FORMAT (1X,A,e9.2)
99997 FORMAT (1X,A,F9.5)
99996 FORMAT (1X,A,I4)
      END
      SUBROUTINE FST(X, FV, N)
      .. Scalar Arguments ..
      INTEGER
```

[NP3546/20A] D01ATF.5

```
.. Array Arguments ..
  real
         FV(N), X(N)
  .. Scalars in Common ..
                PΙ
  INTEGER
                KOUNT
   .. Local Scalars ..
  INTEGER
               I
  .. Intrinsic Functions ..
  INTRINSIC SIN, SQRT
  .. Common blocks ..
  COMMON /TELNUM/PI, KOUNT
  .. Executable Statements ..
  KOUNT = KOUNT + N
  DO 20 I = 1, N
     FV(I) = X(I) * SIN(30.0e0 * X(I)) / SQRT(1.0e0 - X(I) * * 2/(4.0e0 * PI * * 2))
20 CONTINUE
  RETURN
  END
```

9.2 Program Data

None.

9.3 Program Results

```
DO1ATF Example Program Results

A - lower limit of integration = 0.0000
B - upper limit of integration = 6.2832
EPSABS - absolute accuracy requested = 0.00E+00
EPSREL - relative accuracy requested = 0.10E-03

RESULT - approximation to the integral = -2.54326
ABSERR - estimate of the absolute error = 0.13E-04
KOUNT - number of function evaluations = 777
IW(1) - number of subintervals used = 19
```

D01ATF.6 (last) [NP3546/20A]