D01 – Quadrature D01AUF

# NAG Fortran Library Routine Document D01AUF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

## 1 Purpose

D01AUF is an adaptive integrator, especially suited to oscillating, non-singular integrands, which calculates an approximation to the integral of a function f(x) over a finite interval [a, b]:

$$I = \int_{a}^{b} f(x) \, dx.$$

# 2 Specification

```
SUBROUTINE DO1AUF(F, A, B, KEY, EPSABS, EPSREL, RESULT, ABSERR, W, LW,

IW, LIW, IFAIL)

INTEGER KEY, LW, IW(LIW), LIW, IFAIL

real A, B, EPSABS, EPSREL, RESULT, ABSERR, W(LW)

EXTERNAL F
```

# 3 Description

D01AUF is based upon the QUADPACK routine QAG (Piessens *et al.* (1983)). It is an adaptive routine, offering a choice of six Gauss–Kronrod rules. A global acceptance criterion (as defined by Malcolm and Simpson (1976)) is used. The local error estimation is described by Piessens *et al.* (1983).

Because this routine is based on integration rules of high order, it is especially suitable for non-singular oscillating integrands.

The routine requires a user-supplied subroutine to evaluate the integrand at an array of different points and is therefore particularly efficient when the evaluation can be performed in vector mode on a vector-processing machine. Otherwise this algorithm with KEY = 6 is identical to that used by D01AKF.

## 4 References

Malcolm M A and Simpson R B (1976) Local versus global strategies for adaptive quadrature *ACM Trans. Math. Software* **1** 129–146

Piessens R (1973) An algorithm for automatic integration Angew. Inf. 15 399-401

Piessens R, de Doncker-Kapenga E, Überhuber C and Kahaner D (1983) *QUADPACK, A Subroutine Package for Automatic Integration* Springer-Verlag

## 5 Parameters

1: F - SUBROUTINE, supplied by the user.

External Procedure

F must return the values of the integrand f at a set of points.

Its specification is:

```
SUBROUTINE F(X, FV, N)
INTEGER N
real X(N), FV(N)
```

[NP3546/20A] D01AUF.1

1: X(N) - real array

Input

On entry: the points at which the integrand f must be evaluated.

2: FV(N) - real array

Output

On exit: FV(j) must contain the value of f at the point X(j), for j = 1, 2, ..., N.

3: N - INTEGER

Input

On entry: the number of points at which the integrand is to be evaluated. The actual value of N is equal to the number of points in the Kronrod rule (see specification of KEY below).

F must be declared as EXTERNAL in the (sub)program from which D01AUF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: A – real Input

On entry: the lower limit of integration, a.

3: B – real Input

On entry: the upper limit of integration, b. It is not necessary that a < b.

4: KEY – INTEGER Input

On entry: which integration rule is to be used:

if KEY = 1 for the Gauss 7-point and Kronrod 15-point rule,

if KEY = 2 for the Gauss 10-point and Kronrod 21-point rule,

if KEY = 3 for the Gauss 15-point and Kronrod 31-point rule,

if KEY = 4 for the Gauss 20-point and Kronrod 41-point rule,

if KEY = 5 for the Gauss 25-point and Kronrod 51-point rule,

if KEY = 6 for the Gauss 30-point and Kronrod 61-point rule.

Suggested value: KEY = 6.

Constraint: KEY = 1, 2, 3, 4, 5 or 6.

5: EPSABS – *real* Input

*On entry*: the absolute accuracy required. If EPSABS is negative, the absolute value is used. See Section 7.

6: EPSREL – real Input

On entry: the relative accuracy required. If EPSREL is negative, the absolute value is used. See Section 7.

7: RESULT – *real* Output

On exit: the approximation to the integral I.

8: ABSERR – real Output

On exit: an estimate of the modulus of the absolute error, which should be an upper bound |I - RESULT|.

9: W(LW) - real array Output

On exit: details of the computation, as described in Section 8.

D01AUF.2 [NP3546/20A]

D01 – Quadrature D01AUF

10: LW – INTEGER Input

*On entry*: the dimension of the array W as declared in the (sub)program from which D01AUF is called. The value of LW (together with that of LIW below) imposes a bound on the number of sub-intervals into which the interval of integration may be divided by the routine. The number of sub-intervals cannot exceed LW/4. The more difficult the integrand, the larger LW should be.

Suggested value: a value in the range 800 to 2000 is adequate for most problems.

Constraint: LW  $\geq 4$ .

#### 11: IW(LIW) – INTEGER array

Output

On exit: IW(1) contains the actual number of sub-intervals. The rest of the array is used as workspace.

12: LIW – INTEGER Input

On entry: the dimension of the array IW as declared in the (sub)program from which D01AUF is called

The number of sub-intervals into which the interval of integration may be divided cannot exceed LIW.

Suggested value: LIW = LW/4.

Constraint: LIW  $\geq 1$ .

#### 13: IFAIL - INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL  $\neq 0$  on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

## 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

#### IFAIL = 1

The maximum number of subdivisions allowed with the given workspace has been reached without the accuracy requirements being achieved. Look at the integrand in order to determine the integration difficulties. Probably another integrator which is designed for handling the type of difficulty involved must be used. Alternatively, consider relaxing the accuracy requirements specified by EPSABS and EPSREL, or increasing the amount of workspace.

#### IFAIL = 2

Round-off error prevents the requested tolerance from being achieved. Consider requesting less accuracy.

### IFAIL = 3

Extremely bad local integrand behaviour causes a very strong subdivision around one (or more) points of the interval. The same advice applies as in the case of IFAIL = 1.

[NP3546/20A] D01AUF.3

```
\begin{split} \text{IFAIL} &= 4 \\ &\quad \text{On entry, KEY} < 1, \\ &\quad \text{or KEY} > 6. \end{split} \begin{split} \text{IFAIL} &= 5 \\ &\quad \text{On entry, LW} < 4, \\ &\quad \text{or LIW} < 1. \end{split}
```

## 7 Accuracy

The routine cannot guarantee, but in practice usually achieves, the following accuracy:

$$|I - RESULT| \le tol$$

where

$$tol = \max\{|\text{EPSABS}|, |\text{EPSREL}| \times |I|\},$$

and EPSABS and EPSREL are user-specified absolute and relative error tolerances. Moreover, it returns the quantity ABSERR which, in normal circumstances satisfies

$$|I - RESULT| \le ABSERR \le tol.$$

#### 8 Further Comments

If IFAIL  $\neq 0$  on exit, then the user may wish to examine the contents of the array W, which contains the end-points of the sub-intervals used by D01AUF along with the integral contributions and error estimates over these sub-intervals.

Specifically, for  $i=1,2,\ldots,n$ , let  $r_i$  denote the approximation to the value of the integral over the sub-interval  $[a_i,b_i]$  in the partition of [a,b], and  $e_i$  be the corresponding absolute error estimate. Then,  $\int_{a_i}^{b_i} f(x) \, dx \simeq r_i$  and RESULT  $= \sum_{i=1}^n r_i$ . The value of n is returned in IW(1), and the values  $a_i$ ,  $b_i$ ,  $e_i$  and  $r_i$  are stored consecutively in the array W, that is:

$$egin{array}{lll} a_i &=& {
m W}(i), \ b_i &=& {
m W}(n+i), \ e_i &=& {
m W}(2n+i) \ {
m and} \ r_i &=& {
m W}(3n+i). \end{array}$$

# 9 Example

To compute

$$\int_0^{2\pi} x \sin(30x) \cos x \, dx.$$

## 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
D01AUF Example Program Text
Mark 14 Revised. NAG Copyright 1989.
.. Parameters ..
                 NOUT
INTEGER
PARAMETER
                  (NOUT=6)
INTEGER
                 LW, LIW
                 (LW = 800, LIW = LW/4)
PARAMETER
.. Scalars in Common ..
INTEGER
                 KOUNT
.. Local Scalars ..
                 A, ABSERR, B, EPSABS, EPSREL, PI, RESULT
```

D01AUF.4 [NP3546/20A]

D01 – Quadrature D01AUF

```
INTEGER
                       IFAIL, KEY
      .. Local Arrays ..
                       W(LW)
      real
      INTEGER
                        IW(LIW)
      .. External Functions ..
                X01AAF
      EXTERNAL
                       X01AAF
      .. External Subroutines .. EXTERNAL DO1AUF, FST
      .. Common blocks ..
      COMMON
                        /TELNUM/KOUNT
      .. Executable Statements ..
      WRITE (NOUT,*) 'D01AUF Example Program Results'
      PI = X01AAF(0.0e0)
      EPSABS = 0.0e0
      EPSREL = 1.0e-03
      A = 0.0e0
      B = 2.0e0*PI
      KEY = 6
      KOUNT = 0
      IFAIL = -1
      CALL DO1AUF(FST,A,B,KEY,EPSABS,EPSREL,RESULT,ABSERR,W,LW,IW,LIW,
                   IFAIL)
      WRITE (NOUT, *)
      WRITE (NOUT, 99999) 'A
                                   - lower limit of integration = ', A
      WRITE (NOUT,99999) 'A - lower limit or integration = ', A WRITE (NOUT,99999) 'B - upper limit of integration = ', B WRITE (NOUT,99998) 'EPSABS - absolute accuracy requested = ',
     + EPSABS
      WRITE (NOUT, 99998) 'EPSREL - relative accuracy requested = ',
     + EPSREL
      WRITE (NOUT, *)
      IF (IFAIL.NE.O) WRITE (NOUT,99996) 'IFAIL = ', IFAIL
      IF (IFAIL.LE.3) THEN
         WRITE (NOUT,99997) 'RESULT - approximation to the integral = ',
         WRITE (NOUT, 99998) 'ABSERR - estimate of the absolute error = '
     +
           . ABSERR
         WRITE (NOUT, 99996) 'KOUNT - number of function evaluations = '
           . KOUNT
         WRITE (NOUT, 99996) 'IW(1) - number of subintervals used = ',
           IW(1)
      END IF
      STOP
99999 FORMAT (1X,A,F10.4)
99998 FORMAT (1X,A,e9.2)
99997 FORMAT (1X,A,F9.5)
99996 FORMAT (1X,A,I4)
      END
      SUBROUTINE FST(X, FV, N)
      .. Scalar Arguments ..
      INTEGER
      .. Array Arguments ..
                      FV(N), X(N)
      .. Scalars in Common ..
      INTEGER KOUNT
      .. Local Scalars ..
      INTEGER
                     I
      .. Intrinsic Functions ..
      INTRINSIC COS, SIN
      .. Common blocks ..
                      /TELNUM/KOUNT
      COMMON
      .. Executable Statements ..
      KOUNT = KOUNT + N
      DO 20 I = 1, N
         FV(I) = X(I) * (SIN(30.0e0 * X(I))) * COS(X(I))
   20 CONTINUE
      RETURN
```

[NP3546/20A] D01AUF.5

END

# 9.2 Program Data

None.

# 9.3 Program Results

```
DO1AUF Example Program Results

A - lower limit of integration = 0.0000
B - upper limit of integration = 6.2832
EPSABS - absolute accuracy requested = 0.00E+00
EPSREL - relative accuracy requested = 0.10E-02

RESULT - approximation to the integral = -0.20967
ABSERR - estimate of the absolute error = 0.45E-13
KOUNT - number of function evaluations = 427
IW(1) - number of subintervals used = 4
```

D01AUF.6 (last) [NP3546/20A]