NAG Fortran Library Routine Document

F08NWF (CGEBAK/ZGEBAK)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F08NWF (CGEBAK/ZGEBAK) transforms eigenvectors of a balanced matrix to those of the original complex general matrix.

2 Specification

 SUBROUTINE F08NWF(JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)

 ENTRY
 cgebak (JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)

 INTEGER
 N, ILO, IHI, M, LDV, INFO

 real
 SCALE(*)

 complex
 V(LDV,*)

 CHARACTER*1
 JOB, SIDE

The ENTRY statement enables the routine to be called by its LAPACK name.

3 Description

This routine is intended to be used after a complex general matrix A has been balanced by F08NVF (CGEBAL/ZGEBAL), and eigenvectors of the balanced matrix A_{22}'' have subsequently been computed.

For a description of balancing, see the document for F08NVF (CGEBAL/ZGEBAL). The balanced matrix A'' is obtained as $A'' = DPAP^TD^{-1}$, where P is a permutation matrix and D is a diagonal scaling matrix. This routine transforms left or right eigenvectors as follows:

if x is a right eigenvector of A'', $P^T D^{-1} x$ is a right eigenvector of A;

if y is a left eigenvector of A'', $P^T Dy$ is a left eigenvector of A;

4 References

None.

5 Parameters

1: JOB – CHARACTER*1

On entry: this **must** be the same parameter JOB as supplied to F08NVF (CGEBAL/ZGEBAL). *Constraint*: JOB = 'N', 'P', 'S' or 'B'.

2: SIDE – CHARACTER*1

On entry: indicates whether left or right eigenvectors are to be transformed, as follows:

if SIDE = L', left eigenvectors are transformed;

if SIDE = R', right eigenvectors are transformed.

Constraint: SIDE = 'L' or 'R'.

3: N – INTEGER

On entry: n, the number of rows of the matrix of eigenvectors.

Input

Input

Input

Constraint: $N \ge 0$.

- ILO INTEGER Input 4: IHI - INTEGER Input 5: On entry: the values i_{lo} and i_{hi} , as returned by F08NVF (CGEBAL/ZGEBAL). Constraints: 1 < ILO < IHI < N if N > 0, ILO = 1 and IHI = 0 if N = 0. SCALE(*) - *real* array 6: Input Note: the dimension of the array SCALE must be at least max(1, N). On entry: details of the permutations and/or the scaling factors used to balance the original complex general matrix, as returned by F08NVF (CGEBAL/ZGEBAL). 7: M – INTEGER Input On entry: m, the number of columns of the matrix of eigenvectors. Constraint: M > 0. V(LDV,*) – *complex* array Input/Output 8:
 - Note: the second dimension of the array V must be at least max(1, M).

On entry: the matrix of left or right eigenvectors to be transformed.

On exit: the transformed eigenvectors.

9: LDV – INTEGER

On entry: the first dimension of the array V as declared in the (sub)program from which F08NWF (CGEBAK/ZGEBAK) is called.

Constraint: $LDV \ge max(1, N)$.

10: INFO – INTEGER

On exit: INFO = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If INFO = -i, the *i*th parameter had an illegal value. An explanatory message is output, and execution of the program is terminated.

7 Accuracy

The errors are negligible.

8 Further Comments

The total number of real floating-point operations is approximately proportional to nm.

The real analogue of this routine is F08NJF (SGEBAK/DGEBAK).

9 Example

See Section 9 of the document for F08NVF (CGEBAL/ZGEBAL).

Input

Output

INFO < 0