NAG Fortran Library Routine Document G02HBF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G02HBF finds, for a real matrix X of full column rank, a lower triangular matrix A such that $(A^TA)^{-1}$ is proportional to a robust estimate of the covariance of the variables. G02HBF is intended for the calculation of weights of bounded influence regression using G02HDF.

2 Specification

```
SUBROUTINE GO2HBF(UCV, N, M, X, IX, A, Z, BL, BD, TOL, MAXIT, NITMON, NIT, WK, IFAIL)

INTEGER

N, M, IX, MAXIT, NITMON, NIT, IFAIL

real

UCV, X(IX,M), A(M*(M+1)/2), Z(N), BL, BD, TOL,

WK(M*(M+1)/2)

EXTERNAL

UCV
```

3 Description

In fitting the linear regression model

$$y = X\theta + \epsilon$$
,

where y is a vector of length n of the dependent variable,

X is an n by m matrix of independent variables,

 θ is a vector of length m of unknown parameters,

and ϵ is a vector of length n of unknown errors,

it may be desirable to bound the influence of rows of the X matrix. This can be achieved by calculating a weight for each observation. Several schemes for calculating weights have been proposed (see Hampel et al. (1986) and Marazzi (1987a)). As the different independent variables may be measured on different scales one group of proposed weights aims to bound a standardised measure of influence. To obtain such weights the matrix A has to be found such that

$$\frac{1}{n} \sum_{i=1}^{n} u(\|z_i\|_2) z_i z_i^T = I, \quad (I \text{ is the indentity matrix})$$

and

$$z_i = Ax_i$$

where x_i is a vector of length m containing the elements of the ith row of X,

A is an m by m lower triangular matrix,

 z_i is a vector of length m,

and u is a suitable function.

The weights for use with G02HDF may then be computed using

$$w_i = f(||z_i||_2)$$

for a suitable user function f.

G02HBF finds A using the iterative procedure

$$A_k = (S_k + I)A_{k-1},$$

where $S_k = (s_{il})$, for j, l = 1, 2, ..., m is a lower triangular matrix such that

[NP3546/20A] G02HBF.1

$$s_{jl} = \begin{cases} -\min[\max(h_{jl}/n, -BL), \text{BL}], & j > l \\ -\min[\max(\frac{1}{2}(h_{jj}/n - 1), -BD), \text{BD}], & j = l \end{cases}$$

$$h_{jl} = \sum_{i=1}^{n} u(\|z_i\|_2) z_{ij} z_{il}$$

and BD and BL are suitable bounds.

In addition the values of $||z_i||_2$, for i = 1, 2, ..., n, are calculated.

G02HBF is based on routines in ROBETH; see Marazzi (1987a).

4 References

Hampel F R, Ronchetti E M, Rousseeuw P J and Stahel W A (1986) Robust Statistics. The Approach Based on Influence Functions Wiley

Huber P J (1981) Robust Statistics Wiley

Marazzi A (1987a) Weights for bounded influence regression in ROBETH Cah. Rech. Doc. IUMSP, No. 3 ROB 3 Institut Universitaire de Médecine Sociale et Préventive, Lausanne

5 Parameters

1: UCV – *real* FUNCTION, supplied by the user.

External Procedure

Input

UCV must return the value of the function u for a given value of its argument. The value of u must be non-negative.

Its specification is:

1: T - real Input

On entry: the argument for which UCV must be evaluated.

UCV must be declared as EXTERNAL in the (sub)program from which G02HBF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: N – INTEGER Input

On entry: the number, n, of observations.

Constraint: N > 1.

3: M – INTEGER Input

On entry: the number, m, of independent variables.

Constraint: $1 \le M \le N$.

4: X(IX,M) - real array

On entry: the real matrix X, i.e., the independent variables. X(i,j) must contain the ijth element of X, for $i=1,2,\ldots,n,\ j=1,2,\ldots,m$.

5: IX – INTEGER Input

On entry: the first dimension of the array X as declared in the (sub)program from which G02HBF is called.

Constraint: $IX \geq N$.

G02HBF.2 [NP3546/20A]

6: A(M*(M+1)/2) - real array

Input/Output

On entry: an initial estimate of the lower triangular real matrix A. Only the lower triangular elements must be given and these should be stored row-wise in the array.

The diagonal elements must be $\neq 0$, although in practice will usually be > 0. If the magnitudes of the columns of X are of the same order the identity matrix will often provide a suitable initial value for A. If the columns of X are of different magnitudes, the diagonal elements of the initial value of A should be approximately inversely proportional to the magnitude of the columns of X.

On exit: the lower triangular elements of the matrix A, stored row-wise.

7: Z(N) - real array

Output

On exit: the value $||z_i||_2$, i = 1, 2, ..., n.

8: BL - *real*

Input

On entry: the magnitude of the bound for the off-diagonal elements of S_k .

Suggested value: BL = 0.9.

Constraint: BL > 0.

9: BD – *real*

Input

On entry: the magnitude of the bound for the diagonal elements of S_k .

Suggested value: BD = 0.9.

Constraint: BD > 0.

10: TOL – real

Input

On entry: the relative precision for the final value of A. Iteration will stop when the maximum value of $|s_{il}|$ is less than TOL.

Constraint: TOL > 0.0.

11: MAXIT – INTEGER

Input

On entry: the maximum number of iterations that will be used during the calculation of A.

A value of MAXIT = 50 will often be adequate.

Constraint: MAXIT > 0.

12: NITMON – INTEGER

Input

On entry: determines the amount of information that is printed on each iteration.

If NITMON > 0 then the value of A and the maximum value of $|s_{jl}|$ will be printed at the first and every NITMON iterations.

If NITMON ≤ 0 then no iteration monitoring is printed.

When printing occurs the output is directed to the current advisory message unit (see X04ABF).

13: NIT – INTEGER

Output

On exit: the number of iterations performed.

14: WK(M*(M+1)/2) - real array

Workspace

15: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

[NP3546/20A] G02HBF.3

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1
      On entry, N \leq 1,
                M < 1,
      or
      or
                N < M
                IX < N.
      or
IFAIL = 2
      On entry, TOL < 0,
      or
                MAXIT < 0,
                diagonal element of A = 0,
      or
      or
                BL \leq 0,
                BD < 0.
      or
IFAIL = 3
      Value returned by UCV < 0.
IFAIL = 4
```

The routine has failed to converge in MAXIT iterations.

7 Accuracy

On successful exit the accuracy of the results is related to the value of TOL; see Section 5.

8 Further Comments

The existence of A will depend upon the function u; (see Hampel $et\ al.$ (1986) and Marazzi (1987a)), also if X is not of full rank a value of A will not be found. If the columns of X are almost linearly related then convergence will be slow.

9 Example

The example program reads in a matrix of real numbers and computes the Krasker-Welsch weights (see Marazzi (1987a)). The matrix A and the weights are then printed.

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
* GO2HBF Example Program Text

* Mark 14 Revised. NAG Copyright 1989.

* . Parameters ..

INTEGER NIN, NOUT

PARAMETER (NIN=5,NOUT=6)

INTEGER NMAX, MMAX
```

G02HBF.4 [NP3546/20A]

```
PARAMETER
                       (NMAX=5, MMAX=3)
      .. Local Scalars ..
      real
                       BD, BL, TOL
      INTEGER
                       I, IFAIL, IX, J, K, L1, L2, M, MAXIT, MM, N, NIT,
                       NITMON
      .. Local Arrays ..
     real
                       A(MMAX*(MMAX+1)/2), WK(MMAX*(MMAX+1)/2),
                       X(NMAX,MMAX), Z(NMAX)
      .. External Functions ..
      real
                       UCV
      EXTERNAL
                       UCV
      .. External Subroutines ..
      EXTERNAL
                       GO2HBF, XO4ABF
      .. Executable Statements ..
      WRITE (NOUT,*) 'GO2HBF Example Program Results'
      Skip heading in data file
      READ (NIN, *)
      CALL X04ABF(1,NOUT)
      Read in the dimensions of X
      READ (NIN,*) N, M
      IF (N.GT.O .AND. N.LE.NMAX .AND. M.GT.O .AND. M.LE.MMAX) THEN
         Read in the X matrix
         DO 20 I = 1, N
           READ (NIN, \star) (X(I,J),J=1,M)
   2.0
         CONTINUE
         IX = NMAX
         Read in the initial value of A
         MM = (M+1) * M/2
         READ (NIN,*) (A(J),J=1,MM)
         Set the values remaining parameters
         BL = 0.9e0
         BD = 0.9e0
         MAXIT = 50
         TOL = 0.5e-4
         IFAIL = 0
         * Change NITMON to a positive value if monitoring information
           is required *
         NITMON = 0
         CALL GO2HBF(UCV,N,M,X,IX,A,Z,BL,BD,TOL,MAXIT,NITMON,NIT,WK,
                     IFAIL)
         WRITE (NOUT, 99999) 'GO2HBF required', NIT,
           ' iterations to converge
         WRITE (NOUT, *)
         WRITE (NOUT,*) 'Matrix A'
         L2 = 0
         DO 40 J = 1, M
            L1 = L2 + 1
            L2 = L2 + J
            WRITE (NOUT, 99998) (A(K), K=L1, L2)
   40
         CONTINUE
         WRITE (NOUT, *)
         WRITE (NOUT, *) 'Vector Z'
         DO 60 I = 1, N
            WRITE (NOUT, 99998) Z(I)
   60
         CONTINUE
         Calculate Krasker-Welsch weights
         WRITE (NOUT, *)
         WRITE (NOUT,*) 'Vector of weights'
         DO 80 I = 1, N
            Z(I) = 1.0e0/Z(I)
            WRITE (NOUT, 99998) Z(I)
         CONTINUE
      END IF
      STOP
99999 FORMAT (1X,A,I4,A)
99998 FORMAT (1X,6F9.4)
      END
```

[NP3546/20A] G02HBF.5

```
real FUNCTION UCV(T)
UCV function for Krasker-Welsch weights
.. Parameters ..
real
                  UCVC
PARAMETER
                  (UCVC=2.5e0)
.. Scalar Arguments ..
real
.. Local Scalars ..
real
                  PC, PD, Q, Q2
INTEGER
                  IFAIL
.. External Functions ..
       S15ABF, X01AAF, X02AKF
L S15ABF, X01AAF, X02AKF
real
EXTERNAL
.. Intrinsic Functions ..
INTRINSIC EXP, LOG, SQRT
.. Executable Statements ..
UCV = 1.0e0
IF (T.NE.O.0eO) THEN
   Q = UCVC/T
   Q2 = Q*Q
   IFAIL = 0
   PC = S15ABF(Q,IFAIL)
   IF (Q2.LT.-LOG(X02AKF())) THEN
     PD = EXP(-Q2/2.0e0)/SQRT(X01AAF(0.0e0)*2.0e0)
   ELSE
     PD = 0.0e0
   END IF
  UCV = (2.0e0*PC-1.0e0)*(1.0e0-Q2) + Q2 - 2.0e0*Q*PD
END IF
RETURN
END
```

9.2 Program Data

9.3 Program Results

```
GO2HBF Example Program Results
GO2HBF required 16 iterations to converge
Matrix A
   1.3208
  -0.0000
           1.4518
  -0.5753 -0.0000
                    0.9340
Vector Z
   2.4760
   1.9953
   2.4760
   1.9953
   2.5890
Vector of weights
   0.4039
   0.5012
   0.4039
   0.5012
   0.3862
```

G02HBF.6 (last) [NP3546/20A]