

NAG Fortran Library Routine Document

D06BAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

D06BAF generates a boundary mesh on a closed connected subdomain Ω of \mathbb{R}^2 .

2 Specification

```

SUBROUTINE D06BAF(NLINES, COORCH, LINE, FBND, COORUS, NUS, RATE, NCOMP,
1              NLCOMP, LCOMP, NVMAX, NEDMX, NVB, COOR, NEDGE, EDGE,
2              ITRACE, RUSER, IUSER, RWORK, LRWORK, IWORK, LIWORK,
3              IFAIL)
    INTEGER      NLINES, LINE(4,NLINES), NUS, NCOMP, NLCOMP(NCOMP),
1              LCOMP(NLINES), NVMAX, NEDMX, NVB, NEDGE,
2              EDGE(3,NEDMX), ITRACE, IUSER(*), LRWORK,
3              IWORK(LIWORK), LIWORK, IFAIL
    real         COORCH(2,NLINES), FBND, COORUS(2,NUS), RATE(NLINES),
1              COOR(2,NVMAX), RUSER(*), RWORK(LRWORK)
    EXTERNAL     FBND

```

3 Description

Given a closed connected subdomain Ω of \mathbb{R}^2 , whose boundary $\partial\Omega$ is divided by characteristic points into m distinct line segments, D06BAF generates a boundary mesh on $\partial\Omega$. Each line segment may be a straight line, a curve defined by the equation $f(x,y) = 0$, or a polygonal curve defined by a set of given boundary mesh points.

This routine is primarily designed for use with either D06AAF (a simple incremental method) or D06ABF (Delaunay–Voronoi method) or D06ACF (Advancing Front method) to triangulate the interior of the domain Ω . For more details about the boundary and interior mesh generation, consult the D06 Chapter Introduction as well as George and Borouchaki (1998).

This routine is derived from material in the MODULEF package from INRIA (Institut National de Recherche en Informatique et Automatique).

4 References

George P L and Borouchaki H (1998) *Delaunay Triangulation and Meshing: Application to Finite Elements* Editions HERMES, Paris

5 Parameters

- 1: NLINES – INTEGER *Input*
On entry: m , the number of lines that define the boundary of the closed connected subdomain (this equals the number of characteristic points which separate the entire boundary $\partial\Omega$ into lines).
Constraint: $NLINES \geq 1$.
- 2: COORCH(2,NLINES) – **real** array *Input*
On entry: COORCH(1, i) contains the x -coordinate of the i th characteristic point, for $i = 1, \dots, NLINES$; while COORCH(2, i) contains the corresponding y -coordinate.

3: LINE(4,NLINES) – INTEGER array Input

On entry: the description of the lines that define the boundary domain. The line i , for $i = 1, \dots, m$, is defined as follows:

- (a) LINE(1, i): the number of points on the line, including two end-points.
- (b) LINE(2, i): the first end-point of the line. If LINE(2, i) = j , then the coordinates of the first end-point are those stored in COORCH(:, j).
- (c) LINE(3, i): the second end-point of the line. If LINE(3, i) = k , then the coordinates of the second end-point are those stored in COORCH(:, k).
- (d) LINE(4, i): this defines the type of line segment connecting the end-points. Additional information is conveyed by the numerical value of LINE(4, i) as follows:
 - (i) LINE(4, i) > 0, the line is described in the user-supplied function FBND with LINE(4, i) as the index. In this case, the line must be described in the trigonometric (anticlockwise) direction;
 - (ii) LINE(4, i) = 0, the line is a straight line;
 - (iii) if LINE(4, i) < 0, say $(-p)$, then the line is a polygonal arc joining the end-points and interior points specified in COORUS. In this case the line contains the points whose coordinates are stored in COORCH(:, j), COORUS(:, p), COORUS(:, $p + 1$), ..., COORUS(:, $p + r - 3$), COORCH(:, k), where $r = \text{LINE}(1, i)$, $j = \text{LINE}(2, i)$ and $k = \text{LINE}(3, i)$.

Constraints:

$$\begin{aligned}
 2 &\leq \text{LINE}(1, i); \\
 1 &\leq \text{LINE}(2, i) \leq \text{NLINES}; \\
 1 &\leq \text{LINE}(3, i) \leq \text{NLINES}; \\
 \text{LINE}(2, i) &\neq \text{LINE}(3, i), \text{ for } i = 1, \dots, \text{NLINES}.
 \end{aligned}$$

For each line described by the user-supplied function (lines with LINE(4, i) > 0, $i = 1, \dots, \text{NLINES}$) the two end-points (LINE(2, i) and LINE(3, i)) lie on the curve defined by index LINE(4, i) in the user-supplied function FBND, i.e.

$$\begin{aligned}
 &\text{FBND}(\text{LINE}(4, i), \text{COORCH}(1, \text{LINE}(2, i)), \text{COORCH}(2, \text{LINE}(2, i)), \text{RUSER}, \text{IUSER}) = 0 \\
 &\text{and} \\
 &\text{FBND}(\text{LINE}(4, i), \text{COORCH}(1, \text{LINE}(3, i)), \text{COORCH}(2, \text{LINE}(3, i)), \text{RUSER}, \text{IUSER}) = 0, \\
 &\text{for } i = 1, \dots, \text{NLINES}.
 \end{aligned}$$

For all lines described as polygonal arcs (lines with LINE(4, i) < 0, $i = 1, \dots, \text{NLINES}$) the sets of intermediate points (i.e. $[-\text{LINE}(4, i) : -\text{LINE}(4, i) + \text{LINE}(1, i) - 3]$ for all i such that LINE(4, i) < 0) are not overlapping. This can be expressed as:

$$-\text{LINE}(4, i) + \text{LINE}(1, i) - 3 = \sum_{\{j, \text{LINE}(4, j) < 0\}} \{\text{LINE}(1, j) - 2\}$$

or

$$-\text{LINE}(4, i) + \text{LINE}(1, i) - 2 = -\text{LINE}(4, j),$$

for a j such that $j = 1, \dots, \text{NLINES}$, $j \neq i$ and LINE(4, j) < 0.

4: FBND – *real* FUNCTION, supplied by the user. External Procedure

This function must be supplied by the user to calculate the value of the function which describes the curve $\{(x, y) \in \mathbb{R}^2; \text{ such that } f(x, y) = 0\}$ on segments of the boundary for which LINE(4, i) > 0. If there are no boundaries for which LINE(4, i) > 0 FBND will never be referenced by D06BAF and FBND may be the dummy function D06BAD. (D06BAD is included in the NAG Fortran Library and so need not be supplied by the user. Its name may be implementation-dependent: see the Users' Note for your implementation for details.)

Its specification is:

<pre> real FUNCTION FBND(I, X, Y, RUSER, IUSER) INTEGER I, IUSER(*) real X, Y, RUSER(*) </pre>		
1:	I – INTEGER	<i>Input</i>
	<i>On entry:</i> LINE(4, <i>i</i>), the reference index of the line (portion of the contour) <i>i</i> described.	
2:	X – real	<i>Input</i>
3:	Y – real	<i>Input</i>
	<i>On entry:</i> the values of <i>x</i> and <i>y</i> at which $f(x, y)$ is to be evaluated.	
4:	RUSER(*) – real array	<i>Input</i>
5:	IUSER(*) – INTEGER array	<i>Input</i>
	<i>On entry:</i> the user is free to use these arrays to supply information to this function from the calling (sub)program.	

FBND must be declared as EXTERNAL in the (sub)program from which D06BAF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

- 5: COORUS(2,NUS) – **real** array *Input*
On entry: the coordinates of the intermediate points for polygonal arc lines. For a line *i* defined as a polygonal arc (i.e., LINE(4, *i*) < 0), if $p = -\text{LINE}(4, i)$, then COORUS(1, *k*), $k = p, p + 1, \dots, p + \text{LINE}(1, i) - 3$ must contain the *x*-coordinate of the consecutive intermediate points for this line. Similarly COORUS(2, *k*), $k = p, p + 1, \dots, p + \text{LINE}(1, i) - 3$ must contain the corresponding *y*-coordinate.
- 6: NUS – INTEGER *Input*
On entry: the second dimension of the array COORUS as declared in the (sub)program from which D06BAF is called.
Constraint:
$$\text{NUS} \geq \sum_{\{i, \text{LINE}(4, i) < 0\}} \{\text{LINE}(1, i) - 2\}.$$
- 7: RATE(NLINES) – **real** array *Input*
On entry: RATE(*i*) is the geometric progression ratio between the points to be generated on the line *i*, for $i = 1, \dots, m$ and LINE(4, *i*) ≥ 0. RATE(*i*) is not referenced if LINE(4, *i*) < 0.
Constraint: RATE(*i*) > 0; for $i = 1, \dots, \text{NLINES}$ and LINE(4, *i*) ≥ 0.
- 8: NCOMP – INTEGER *Input*
On entry: *n*, the number of separately connected components of the boundary.
Constraint: NCOMP ≥ 1.
- 9: NLCOMP(NCOMP) – INTEGER array *Input*
On entry: |NLCOMP(*k*)| is the number of line segments in component *k* of the contour. The line *i* of component *k* runs in the direction LINE(2, *i*) to LINE(3, *i*) if NLCOMP(*k*) > 0, and in the opposite direction otherwise; for $k = 1, \dots, n$.
Constraint:

$$1 \leq |\text{NLCOMP}(k)| \leq \text{NLINES}, \text{ for } k = 1, \dots, \text{NCOMP},$$

$$\sum_{k=1}^n |\text{NLCOMP}(k)| = \text{NLINES}.$$

- 10: LCOMP(NLINES) – INTEGER array *Input*
On entry: LCOMP($l1 : l2$), where $l2 = \sum_{i=1}^k |\text{NLCOMP}(i)|$ and $l1 = l2 + 1 - |\text{NLCOMP}(k)|$ is the list of line numbers for the k th components of the boundary, for $k = 1, \dots, \text{NCOMP}$.
Constraint: LCOMP must hold a valid permutation of the integers $[1, \text{NLINES}]$.
- 11: NVMAX – INTEGER *Input*
On entry: the maximum number of the boundary mesh vertices to be generated.
Constraint: NVMAX \geq NLINES.
- 12: NEDMX – INTEGER *Input*
On entry: the maximum number of boundary edges in the boundary mesh to be generated.
Constraint: NEDMX \geq 1.
- 13: NVB – INTEGER *Output*
On exit: the total number of boundary mesh vertices generated.
- 14: COOR(2,NVMAX) – *real* array *Output*
On exit: COOR(1, i) will contain the x -coordinate of the i th boundary mesh vertex generated, for $i = 1, \dots, \text{NVB}$; while COOR(2, i) will contain the corresponding y -coordinate.
- 15: NEDGE – INTEGER *Output*
On entry: the total number of boundary edges in the boundary mesh.
- 16: EDGE(3,NEDMX) – INTEGER array *Output*
On exit: the specification of the boundary edges. EDGE(1 : 2, j) will contain the vertex number of the two end-points of the j th boundary edge. EDGE(3, j) is a reference number for the j th boundary edge and
 $\text{EDGE}(3, j) = \text{LINE}(4, i)$, where i and j are such that the j th edges is part of the i th line of the boundary and $\text{LINE}(4, i) \geq 0$;
 $\text{EDGE}(3, j) = 100 + |\text{LINE}(4, i)|$, where i and j are such that the j th edges is part of the i th line of the boundary and $\text{LINE}(4, i) < 0$.
- 17: ITRACE – INTEGER *Input*
On entry: the level of trace information required from D06BAF as follows:
if ITRACE ≤ 0 , no output is generated.
if ITRACE = 1, then output from the boundary mesh generator is printed on the current advisory message unit (see X04ABF). This output contains the input informations of each line and each connected component of the boundary.
if ITRACE > 1 , then the output is similar to that produced when ITRACE = 1, but the coordinates of the generated vertices on the boundary are also output.
if ITRACE = -1, then an analysis of the output boundary mesh is printed on the current advisory message unit. This analysis includes the orientation (clockwise or anticlockwise) of each connected component of the boundary. Those informations could be of interest to the user, especially if an interior meshing is carried out using the output of this routine, calling either D06AAF, D06ABF or D06ACF.

Users are advised to set ITRACE = 0, unless they are experienced with Finite Element meshes generation.

- 18: RUSER(*) – *real* array *Input*
Note: the dimension of the array RUSER must be at least 1.
On entry: the user is free to use these arrays to supply information to the user-supplied function FBND from the calling (sub)program.
- 19: IUSER(*) – INTEGER array *Input*
Note: the dimension of the array IUSER must be at least 1.
- 20: RWORK(LRWORK) – *real* array *Workspace*
 21: LRWORK – INTEGER *Input*
On entry: the dimension of the array RWORK as declared in the (sub)program from which D06BAF is called.
Constraint: $LRWORK \geq 2 \times (NLINES + NUS) + 2 \times \max_{i=1,\dots,m} \{LINE(1, i)\} \times NLINES$.
- 22: IWORK(LIWORK) – INTEGER array *Workspace*
 23: LIWORK – INTEGER *Input*
On entry: the dimension of the array IWORK as declared in the (sub)program from which D06BAF is called.
Constraint: $LIWORK \geq \sum_{\{i, LINE(4,i) < 0\}} \{LINE(1, i) - 2\} + 8 \times NLINES + NVMAX + 3 \times NEDMX + 2 \times NUS$.
- 24: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

- On entry, NLINES < 1;
 or NVMAX < NLINES;
 or NEDMX < 1;
 or NCOMP < 1;
 or $LRWORK < 2 \times (NLINES + NUS) + 2 \times \max_{i=1,\dots,m} \{LINE(1, i)\} \times NLINES$;
 or
 $LIWORK < \sum_{\{i, LINE(4,i) < 0\}} \{LINE(1, i) - 2\} + 8 \times NLINES + NVMAX + 3 \times NEDMX + 2 \times NUS$;
 or $NUS < \sum_{\{i, LINE(4,i) < 0\}} \{LINE(1, i) - 2\}$;
 or RATE(i) < 0.0 for some $i = 1, \dots, NLINES$ with $LINE(4, i) \geq 0$;
 or $LINE(1, i) < 2$ for some $i = 1, \dots, NLINES$;
 or $LINE(2, i) < 1$ or $LINE(2, i) > NLINES$ for some $i = 1, \dots, NLINES$;

- or $\text{LINE}(3, i) < 1$ or $\text{LINE}(3, i) > \text{NLINES}$ for some $i = 1, \dots, \text{NLINES}$;
- or $\text{LINE}(2, i) = \text{LINE}(3, i)$ for some $i = 1, \dots, \text{NLINES}$;
- or $\text{NLCOMP}(k) = 0$, or $|\text{NLCOMP}(k)| > \text{NLINES}$ for a $k = 1, \dots, \text{NCOMP}$;
- or $\sum_{k=1}^n |\text{NLCOMP}(k)| \neq \text{NLINES}$;
- or LCOMP does not represent a valid permutation of the integers in $[1, \text{NLINES}]$;
- or one of the end-points for a line i described by the user-supplied function (lines with $\text{LINE}(4, i) > 0$, for $i = 1, \dots, \text{NLINES}$) does not belong to the corresponding curve in the user-supplied function FBND;
- or the intermediate points for the lines described as polygonal arcs (lines with $\text{LINE}(i) < 0$, for $i = 1, \dots, \text{NLINES}$) are overlapping.

IFAIL = 2

An error has occurred during the generation of the boundary mesh. It appears that NEDMX is not large enough, so the user is advised to increase the value of NEDMX.

IFAIL = 3

An error has occurred during the generation of the boundary mesh. It appears that NVMAX is not large enough, so the user is advised to increase the value of NVMAX.

IFAIL = 4

An error has occurred during the generation of the boundary mesh. Check the definition of each line (the argument LINE) and each connected component of the boundary (the arguments NLCOMP, and LCOMP, as well as the coordinates of the characteristic points. Setting ITRACE > 0 may provide more details.

7 Accuracy

Not applicable.

8 Further Comments

The boundary mesh generation technique in this routine has a ‘tree’ structure. The boundary should be partitioned into geometrically simple segments (straight lines or curves) delimited by characteristic points. Then, the lines should be assembled into connected component of the boundary domain.

Using this strategy, the inputs to that routine can be built up, following the requirements stated in the arguments description section:

the characteristic and the user-supplied intermediate points:

NLINES, NUS, COORCH and COORUS;

the characteristic lines:

LINE, FBND, RATE

finally the assembly of lines into the connected components of the boundary:

NCOMP, and

NLCOMP, LCOMP.

The example below details the use of this strategy.

9 Example

The NAG logo is taken as an example of a geometry with holes. The boundary has been partitioned in 40 lines characteristic points; including 4 for the exterior boundary and 36 for the logo itself. All line

geometry specifications have been considered, see the argument description of LINE, including 4 lines defined as polygonal arc, 4 defined by a user-supplied function and all the others are straight lines.

Figure 1 top represents the boundary mesh of the NAG logo; there are 259 nodes and 259 edges. The Figure 1 middle and bottom represent the final mesh built using respectively the Delaunay-Voronoi (D06ABF) and the Advancing front (D06ACF) method.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      D06BAF Example Program Text
*      Mark 20 Release. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER                NIN, NOUT
      PARAMETER              (NIN=5,NOUT=6)
      INTEGER                NEDMX, NVMAX, NLINESX, NUS, NCOMPX, NVIMX,
+      MAXCAN, LRWORK, LIWORK
      PARAMETER              (NEDMX=300,NVMAX=1000,NLINESX=50,NUS=100,
+      NCOMPX=5,NVIMX=20,MAXCAN=10000,
+      LRWORK=12*NVMAX+3*MAXCAN+15,
+      LIWORK=8*NEDMX+55*NVMAX+MAXCAN+78)
*      .. Local Scalars ..
      real                  XO, XA, XB, XMAX, XMIN, YO, YMAX, YMIN
      INTEGER                I, IFAIL, ITRACE, J, K, NCOMP, NEDGE, NELT,
+      NLINES, NPROPA, NV, NVB, NVINT, REFTK
      CHARACTER              PMESH
*      .. Local Arrays ..
      real                  COOR(2,NVMAX), COORCH(2,NLINESX), COORUS(2,NUS),
+      RATE(NLINESX), RUSER(4), RWORK(LRWORK),
+      WEIGHT(NVIMX)
      INTEGER                CONN(3,2*NVMAX+5), EDGE(3,NEDMX), IUSER(1),
+      IWORK(LIWORK), LCOMP(NLINESX), LINE(4,NLINESX),
+      NLCOMP(NCOMPX)
*      .. External Functions ..
      real                  FBND
      EXTERNAL               FBND
*      .. External Subroutines ..
      EXTERNAL               D06ABF, D06ACF, D06BAF
*      .. Intrinsic Functions ..
      INTRINSIC              ABS
*      .. Executable Statements ..
*
      WRITE (NOUT,*) 'D06BAF Example Program Results'
      WRITE (NOUT,*)

*
*      Skip heading in data file
*
      READ (NIN,*)

*
*      Initialise boundary mesh inputs:
*      the number of line and of the characteristic points of
*      the boundary mesh
*
      READ (NIN,*) NLINES

*
*      The ellipse boundary which envelops the NAg Logo
*      the N, the A and the G
*
      READ (NIN,*) (COORCH(1,J),J=1,NLINES)
      READ (NIN,*) (COORCH(2,J),J=1,NLINES)

*
      READ (NIN,*) (COORUS(1,J),J=1,4)
      READ (NIN,*) (COORUS(2,J),J=1,4)

*
*      The Lines of the boundary mesh
*
      READ (NIN,*) ((LINE(I,J),I=1,4),RATE(J),J=1,NLINES)
```

```

*
*   The number of connected components to the boundary
*   and their informations
*
      READ (NIN,*) NCOMP
      J = 1
      DO 20 I = 1, NCOMP
        READ (NIN,*) NLCOMP(I)
*
        READ (NIN,*) (LCOMP(K),K=J,J+ABS(NLCOMP(I))-1)
        J = J + ABS(NLCOMP(I))
20  CONTINUE
*
      READ (NIN,*) PMESH
*
*   Data passed to the user-supplied function
*
      XMIN = COORCH(1,4)
      XMAX = COORCH(1,2)
      YMIN = COORCH(2,1)
      YMAX = COORCH(2,3)
*
      XA = (XMAX-XMIN)/2.e0
      XB = (YMAX-YMIN)/2.e0
*
      XO = (XMIN+XMAX)/2.e0
      YO = (YMIN+YMAX)/2.e0
*
      RUSER(1) = XA
      RUSER(2) = XB
      RUSER(3) = XO
      RUSER(4) = YO
      IUSER(1) = 0
*
      ITRACE = -1
*
*   Call to the boundary mesh generator
*
      IFAIL = 0
*
      CALL D06BAF(NLINES,COORCH,LINE,FBND,COORUS,NUS,RATE,NCOMP,NLCOMP,
+               LCOMP,NVMAX,NEDMX,NVB,COOR,NEDGE,EDGE,ITRACE,RUSER,
+               IUSER,RWORK,LRWORK,IWORK,LIWORK,IFAIL)
*
      IF (PMESH.EQ.'N') THEN
        WRITE (NOUT,*) 'Boundary mesh characteristics'
        WRITE (NOUT,99999) 'NVB =', NVB
        WRITE (NOUT,99999) 'NEDGE =', NEDGE
      ELSE IF (PMESH.EQ.'Y') THEN
*
*   Output the mesh to view it using the NAG Graphics Library
*
        WRITE (NOUT,99998) NVB, NEDGE
*
        DO 40 I = 1, NVB
          WRITE (NOUT,99997) I, COOR(1,I), COOR(2,I)
40      CONTINUE
*
        DO 60 I = 1, NEDGE
          WRITE (NOUT,99996) I, EDGE(1,I), EDGE(2,I), EDGE(3,I)
60      CONTINUE
      ELSE
        WRITE (NOUT,*) 'Problem with the printing option Y or N'
        STOP
      END IF
*
*   Initialise mesh control parameters
*
      ITRACE = 0
      NPROPA = 1
      NVINT = 0

```



```

      IFAIL = 0
*
*   Call to the 2D Delaunay-Voronoi mesh generator
*
      CALL D06ABF(NVB,NVINT,NVMAX,NEDGE,EDGE,NV,NELT,COOR,CONN,WEIGHT,
+               NPROPA,ITRACE,RWORK,LRWORK,IWORK,LIWORK,IFAIL)
*
      IF (PMESH.EQ.'N') THEN
        WRITE (NOUT,*)
+       'Complete mesh (via the 2D Delaunay-Voronoi mesh'
        WRITE (NOUT,*) 'generator) characteristics'
        WRITE (NOUT,99999) 'NV   =', NV
        WRITE (NOUT,99999) 'NELT =', NELT
      ELSE IF (PMESH.EQ.'Y') THEN
*
*   Output the mesh to view it using the NAG Graphics Library
*
        WRITE (NOUT,99998) NV, NELT
        DO 80 I = 1, NV
          WRITE (NOUT,99995) COOR(1,I), COOR(2,I)
80      CONTINUE
*
        REFTK = 0
        DO 100 K = 1, NELT
          WRITE (NOUT,99994) CONN(1,K), CONN(2,K), CONN(3,K), REFTK
100     CONTINUE
        END IF
*
*   Call to the 2D Advancing front mesh generator
*
      IFAIL = 0
*
      CALL D06ACF(NVB,NVINT,NVMAX,NEDGE,EDGE,NV,NELT,COOR,CONN,WEIGHT,
+               ITRACE,RWORK,LRWORK,IWORK,LIWORK,IFAIL)
*
      IF (PMESH.EQ.'N') THEN
        WRITE (NOUT,*) 'Complete mesh (via the 2D Advancing front mesh'
        WRITE (NOUT,*) 'generator) characteristics'
        WRITE (NOUT,99999) 'NV   =', NV
        WRITE (NOUT,99999) 'NELT =', NELT
      ELSE IF (PMESH.EQ.'Y') THEN
*
*   Output the mesh to view it using the NAG Graphics Library
*
        WRITE (NOUT,99998) NV, NELT
        DO 120 I = 1, NV
          WRITE (NOUT,99995) COOR(1,I), COOR(2,I)
120     CONTINUE
*
        REFTK = 0
        DO 140 K = 1, NELT
          WRITE (NOUT,99994) CONN(1,K), CONN(2,K), CONN(3,K), REFTK
140     CONTINUE
        END IF
*
      STOP
*
99999 FORMAT (1X,A,I6)
99998 FORMAT (1X,2I10)
99997 FORMAT (2X,I4,2(2X,E12.6))
99996 FORMAT (1X,4I4)
99995 FORMAT (2(2X,E12.6))
99994 FORMAT (1X,4I10)
      END
*
      real FUNCTION FBND(I,X,Y,RUSER,IUSER)
*
      .. Scalar Arguments ..
      real X, Y
      INTEGER I
*
      .. Array Arguments ..
      real RUSER(*)

```

```

      INTEGER          IUSER(*)
*      .. Local Scalars ..
      real             RADIUS2, X0, XA, XB, Y0
*      .. Executable Statements ..
*
      XA = RUSER(1)
      XB = RUSER(2)
      X0 = RUSER(3)
      Y0 = RUSER(4)
*
      FBND = 0.e0
      IF (I.EQ.1) THEN
*
*      line 1,2,3, and 4: ellipse centred in (X0,Y0) with
*      XA and XB as coefficients
*
         FBND = ((X-X0)/XA)**2 + ((Y-Y0)/XB)**2 - 1.e0
      ELSE IF (I.EQ.2) THEN
*
*      line 24, 27, 33 and 38 are a circle centred in (X0,Y0)
*      with radius SQRT(RADIUS2)
*
         X0 = 20.5e0
         Y0 = 4.e0
         RADIUS2 = 4.25e0
         FBND = (X-X0)**2 + (Y-Y0)**2 - RADIUS2
      ELSE IF (I.EQ.3) THEN
         X0 = 17.e0
         Y0 = 8.5e0
         RADIUS2 = 5.e0
         FBND = (X-X0)**2 + (Y-Y0)**2 - RADIUS2
      ELSE IF (I.EQ.4) THEN
         X0 = 17.e0
         Y0 = 8.5e0
         RADIUS2 = 5.e0
         FBND = (X-X0)**2 + (Y-Y0)**2 - RADIUS2

      ELSE IF (I.EQ.5) THEN
         X0 = 19.5e0
         Y0 = 4.e0
         RADIUS2 = 1.25e0
         FBND = (X-X0)**2 + (Y-Y0)**2 - RADIUS2
      END IF
*
      RETURN
      END

```

9.2 Program Data

D06BAF Example Program Data

```

40                                     :NLINEs (m)
   9.5000  33.0000   9.5000 -14.0000  -4.0000  -2.0000   2.0000
   4.0000   2.0000  -2.0000  -4.0000  -2.0000   2.0000   4.0000
   7.0000   9.0000  13.0000  16.0000   9.0000  12.0000   7.0000
  10.0000  18.0000  21.0000  17.0000  20.0000  16.0000  20.0000
  15.5000  16.0000  18.0000  21.0000  16.0000  18.0000  18.5811
  21.0000  17.0000  20.0000  20.5000  23.0000                                     : (COORCH(1,1:m))
  -1.0000   7.5000  16.0000   7.5000   3.0000   3.0000   3.0000
   3.0000   7.0000   8.0000  12.0000  12.0000  12.0000  12.0000
   3.0000   3.0000   3.0000   3.0000   5.0000   5.0000  12.0000
  12.0000   2.0000   2.0000   3.0000   3.0000   5.0000   5.0000
   6.0000   6.0000   6.0000   6.0000   6.5000   6.5000  10.0811
  10.0811  10.7361  10.7361  12.0000  12.0000                                     : (COORCH(2,1:m))
  -2.6667  -3.3333   3.3333   2.6667                                     : (COORUS(1,1:4))
   3.0000   3.0000   3.0000   3.0000                                     : (COORUS(2,1:4))
15  1  2  1  0.9500  15  2  3  1  1.0500
15  3  4  1  0.9500  15  4  1  1  1.0500
   4  6  5 -1  1.0000  10 10  6  0  1.0000
  10  7 10  0  1.0000   4  8  7 -3  1.0000
  15 14  8  0  1.0000   4 13 14  0  1.0000

```

```

10  9 13  0  1.0000  10 12  9  0  1.0000
 4 11 12  0  1.0000  15  5 11  0  1.0000
 4 16 15  0  1.0000   7 19 16  0  1.0000
 4 20 19  0  1.0000   7 17 20  0  1.0000
 4 18 17  0  1.0000  13 22 18  0  1.0000
 5 21 22  0  1.0000  13 15 21  0  1.0000
 4 24 23  0  1.0000  10 24 32  2  1.0000
 4 31 32  0  1.0000   4 34 31  0  1.0000
10 34 35  3  1.0000   4 36 35  0  1.0000
 4 40 36  0  1.0000   4 39 40  0  1.0000
 4 38 39  0  1.0000   4 37 38  0  1.0000
10 37 33  4  1.0000   4 30 33  0  1.0000
 4 29 30  0  1.0000   4 27 29  0  1.0000
 4 28 27  0  1.0000  10 26 28  5  1.0000
 4 25 26  0  1.0000   4 23 25  0  1.0000 : (LINE(:,j),RATE(j),j=1,m)
 4                                     :NCOMP (n, number of contours)
 4                                     :number of lines in contour 1
 1  2  3  4                                     :lines of contour 1
10                                     :number of lines in contour 2
14 13 12 11 10  9  8  7  6  5                                     :lines of contour 2
 8                                     :number of lines in contour 3
22 21 20 19 18 17 16 15                                     :lines of contour 3
18                                     :number of lines in contour 4
30 29 28 27 26 25 24 23 40 39
38 37 36 35 34 33 32 31
'N'                                     :lines of contour 4
                                     :Printing option 'Y' or 'N'

```

9.3 Program Results

D06BAF Example Program Results

```

ANALYSIS OF THE BOUNDARY CREATED:
THE BOUNDARY MESH CONTAINS      259 VERTEX AND      259 EDGES
THERE ARE      4 COMPONENTS CONNECTED THE BOUNDARY
THE  1-st COMPONENT CONTAINS      4 LINES IN ANTICLOCKWISE ORIENTATION
THE  2-nd COMPONENT CONTAINS     10 LINES IN CLOCKWISE ORIENTATION
THE  3-rd COMPONENT CONTAINS      8 LINES IN CLOCKWISE ORIENTATION
THE  4-th COMPONENT CONTAINS     18 LINES IN CLOCKWISE ORIENTATION
Boundary mesh characteristics
NVB   =    259
NEDGE =    259
Complete mesh (via the 2D Delaunay-Voronoi mesh
generator) characteristics
NV    =    652
NELT  =   1049
Complete mesh (via the 2D Advancing front mesh
generator) characteristics
NV    =    662
NELT  =   1069

```




Figure 1

The boundary mesh (top), the Delaunay–Voronoi mesh (middle) and the Advancing Front mesh (bottom) of the NAG logo geometry
