NAG Fortran Library Routine Document

G13AGF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

G13AGF accepts a series of new observations of a time series, the model of which is already fully specified, and updates the 'state set' information for use in constructing further forecasts. The previous specifications of the time series model should have been obtained by using G13AEF or G13AFF to estimate the relevant parameters. The supplied state set will originally have been produced by G13AEF or G13AFF, but may since have been updated by earlier calls to G13AGF.

A set of residuals corresponding to the new observations is returned. These may be of use in checking that the new observations conform to the previously fitted model.

2 Specification

SUBROUTINE G13AGF(ST, NST, MR, PAR, NPAR, C, ANX, NUV, ANEXR, WA, NWA,1IFAIL)INTEGERNST, MR(7), NPAR, NUV, NWA, IFAILrealST(NST), PAR(NPAR), C, ANX(NUV), ANEXR(NUV), WA(NWA)

3 Description

The time series model is specified as outlined in Section 3 of the document for G13AEF or Section 3 of the document for G13AFF. This also describes how the state set, which contains the minimum amount of time series information needed to construct forecasts, is made up of

- (i) the differenced series w_t (uncorrected for the constant c), for $(N P \times s) < t \le N$,
- (ii) the d' values required to reconstitute the original series x_t from the differenced series w_t ,
- (iii) the intermediate series e_t , for $(N \max(p, Q \times s)) < t \le N$, and
- (iv) the residual series a_t , for $(N-q) < t \le N$.

If the number of original undifferenced observations was n, then $d' = d + (D \times s)$ and N = n - d'.

To update the state set, given a number of new undifferenced observations x_t , t = n + 1, n + 2, ..., n + k, the four series above are first reconstituted.

Differencing and residual calculation operations are then applied to the new observations and k new values of w_t, e_t and a_t are derived.

The first k values in these three series are then discarded and a new state set is obtained.

The residuals in the a_t series corresponding to the k new observations are preserved in an output array. The parameters of the time series model are not changed in this routine.

4 References

None.

5 **Parameters**

1: ST(NST) – *real* array

On entry: the state set derived from G13AEF or G13AFF, or as modified using earlier calls of G13AGF.

On exit: the updated values of the state set.

2: NST – INTEGER

On entry: the number of values in the state set array ST.

Constraint: NST = $P \times s + D \times s + d + q + \max(p, Q \times s)$. (As returned by G13AEF or G13AFF).

3: MR(7) – INTEGER array

On entry: the orders vector (p, d, q, P, D, Q, s) of the ARIMA model, in the usual notation.

Constraints:

 $\begin{array}{l} p, d, q, P, D, Q, s \geq 0, \\ p+q+P+Q > 0, \\ s \neq 1, \\ \text{if } s = 0, \text{ then } P+D+Q = 0, \\ \text{if } s > 1, \text{ then } P+D+Q > 0. \end{array}$

4: PAR(NPAR) – *real* array

On entry: the estimates of the p values of the ϕ parameters, the q values of the θ parameters, the P values of the Φ parameters and the Q values of the Θ parameters in the model – in that order, using the usual notation.

5:	NPAR – INTEGER	Input
	On entry: the number of ϕ , θ , Φ , Θ parameters in the model.	
	Constraint: NPAR = $p + q + P + Q$.	
6:	C – real	Input
	On entry: the constant to be subtracted from the differenced data.	
7:	ANX(NUV) – <i>real</i> array	Input
	On entry: the new undifferenced observations which are to be used to update ST.	
8:	NUV – INTEGER	Input
	On entry: the number of new observations in ANX, k.	
9:	ANEXR(NUV) – <i>real</i> array	Output
	On exit: the residuals corresponding to the new observations in ANX.	
10: 11:	WA(NWA) – <i>real</i> array NWA – INTEGER	Workspace Input
	On entry: the dimension of the array WA as declared in the (sub)program from which called	G13AGF is

Constraint: NWA \geq (4 × NPAR + 3 × NST).

Input

Input

Input

Input/Output

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, NPAR $\neq p + q + P + Q$, or the orders vector MR is invalid (check the constraints in Section 5).

IFAIL = 2

On entry, NST $\neq P \times s + D \times s + d + q + \max(Q \times s, p)$.

IFAIL = 3

On entry, NUV ≤ 0 .

IFAIL = 4

On entry, NWA < $4 \times NPAR + 3 \times NST$.

7 Accuracy

The computations are believed to be stable.

8 Further Comments

The time taken by the routine is approximately proportional to NUV \times NPAR.

9 Example

The following program is based on data derived from a study of monthly airline passenger totals (in thousands) to which a logarithmic transformation had been applied. The time series model was based on seasonal and non-seasonal differencing both of order 1, with seasonal period 12. The number of parameters estimated was two: a non-seasonal moving average parameter θ_1 with value 0.327 and a seasonal moving average parameter Θ_1 with value 0.6270. There was no constant correction. These, together with the state set array, were obtained using G13AEF.

Twelve new observations are supplied. The routine updates the state set and outputs a set of residuals corresponding to the new observations.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
G13AGF Example Program Text
*
      Mark 14 Revised. NAG Copyright 1989.
*
      .. Parameters ..
                       NPMAX, NSTMAX, NNVMAX, NWAMAX
      INTEGER
      PARAMETER
                       (NPMAX=10,NSTMAX=50,NNVMAX=50,NWAMAX=150)
      INTEGER
                       NIN, NOUT
                       (NIN=5,NOUT=6)
      PARAMETER
      .. Local Scalars ..
      real
                       С
      INTEGER
                       I, IFAIL, NNV, NPAR, NST, NWA
      .. Local Arrays ..
*
      real
                       ANV(NNVMAX), ANVR(NNVMAX), PAR(NPMAX),
                       ST(NSTMAX), WA(NWAMAX)
      INTEGER
                       MR(7)
*
      .. External Subroutines ..
      EXTERNAL
                   G13AGF
      .. Intrinsic Functions ..
      INTRINSIC
                     MAX
      .. Executable Statements ..
4
      WRITE (NOUT, *) 'G13AGF Example Program Results'
      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) NNV
      READ (NIN, \star) (MR(I), I=1,7)
      NPAR = MR(1) + MR(3) + MR(4) + MR(6)
      NST = MR(4) * MR(7) + MR(5) * MR(7) + MR(2) + MR(3) + MAX(MR(1),MR(6))
     +
           *MR(7))
      NWA = 4 * NPAR + 3 * NST
      IF (NNV.GT.O .AND. NNV.LE.NNVMAX .AND. NPAR.GT.O .AND. NPAR.LE.
          NPMAX .AND. NST.GT.O .AND. NST.LE.NSTMAX) THEN
         READ (NIN,*) (PAR(I),I=1,NPAR), C
         READ (NIN,*) (ST(I),I=1,NST)
         READ (NIN,*) (ANV(I),I=1,NNV)
         IFAIL = 0
         CALL G13AGF(ST,NST,MR,PAR,NPAR,C,ANV,NNV,ANVR,WA,NWA,IFAIL)
*
         WRITE (NOUT,*)
         WRITE (NOUT, *)
           'The updated state set array now holds the values'
     +
         WRITE (NOUT, 99999) (ST(I), I=1, NST)
         WRITE (NOUT, *)
         WRITE (NOUT, 99998) 'The residuals corresponding to the', NNV
         WRITE (NOUT, *) 'values used to update the system are'
         WRITE (NOUT, 99999) (ANVR(I), I=1, NNV)
      END IF
      STOP
*
99999 FORMAT (1X,8F8.4)
99998 FORMAT (1X,A,I3,A)
      END
```

9.2 Program Data

G13AGF Example Program Data 12 0 1 1 0 1 1 12 0.3270 0.6270 0.0000 0.0118 -0.0669 0.1296 -0.0394 0.0422 0.1809 0.1211 0.0281 -0.2231 -0.1181 -0.1468 0.0835 5.8201 -0.0157 -0.0361 -0.0266 -0.0199 0.0298 0.0290 0.0147 0.0373 -0.0931 0.0223 -0.0172 -0.0353 -0.0413 5.8861 5.8348 6.0064 5.9814 6.0403 6.1570 6.3063 6.3261 6.1377 6.0088 5.8916 6.0039

9.3 Program Results

G13AGF Example Program Results

The updated state set array now holds the values 0.0660 -0.0513 0.1716 -0.0250 0.0589 0.1167 0.1493 0.0198 -0.1884 -0.1289 -0.1172 0.1123 6.0039 0.0444 -0.0070 0.0253 0.0019 0.0354 -0.0460 0.0374 0.0151 -0.0237 0.0032 0.0188 0.0067 0.0126 The residuals corresponding to the 12 values used to update the system are 0.0309 0.0031 0.0263 0.0105 0.0388 -0.0333 0.0265 0.0238 -0.0159 -0.0020 0.0182 0.0126