# NAG Fortran Library Routine Document S18CFF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

#### 1 Purpose

S18CFF returns a value of the scaled modified Bessel function  $e^{-|x|}I_1(x)$  via the routine name.

# 2 Specification

#### 3 Description

This routine evaluates an approximation to  $e^{-|x|}I_1(x)$ , where  $I_1$  is a modified Bessel function of the first kind. The scaling factor  $e^{-|x|}$  removes most of the variation in  $I_1(x)$ .

The routine uses the same Chebyshev expansions as S18AFF, which returns the unscaled value of  $I_1(x)$ .

### 4 References

Abramowitz M and Stegun I A (1972) Handbook of Mathematical Functions (3rd Edition) Dover Publications

#### 5 Parameters

1: X - real Input

On entry: the argument x of the function.

2: IFAIL – INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

There are no actual failure exits from this routine. IFAIL is always set to zero. This parameter is included for compatibility with other routines in this chapter.

#### 7 Accuracy

Relative errors in the argument are attenuated when propagated into the function value. When the accuracy of the argument is essentially limited by the *machine precision*, the accuracy of the function value will be similarly limited by at most a small multiple of the *machine precision*.

[NP3546/20A] S18CFF.1

#### **8** Further Comments

None.

# 9 Example

The example program reads values of the argument x from a file, evaluates the function at each value of x and prints the results.

# 9.1 Program Text

**Note:** the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
S18CFF Example Program Text
      Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
*
      INTEGER
                       NIN, NOUT
      PARAMETER
                        (NIN=5, NOUT=6)
      .. Local Scalars ..
      real
      INTEGER
                       TFATL
      .. External Functions ..
      real
                       S18CFF
      EXTERNAL
                       S18CFF
      .. Executable Statements ..
      WRITE (NOUT,*) 'S18CFF Example Program Results'
      Skip heading in data file
      READ (NIN, *)
      WRITE (NOUT,*)
      WRITE (NOUT, *) '
                                       Y
                                                  IFAIL'
      WRITE (NOUT,*)
   20 READ (NIN, \star, END=40) X
      IFAIL = 1
      Y = S18CFF(X,IFAIL)
      WRITE (NOUT, 99999) X, Y, IFAIL
      GO TO 20
   40 STOP
99999 FORMAT (1X,1P,2e12.3,17)
      END
```

#### 9.2 Program Data

```
S18CFF Example Program Data
0.0
0.5
1.0
3.0
6.0
10.0
1000.0
-1.0
```

S18CFF.2 [NP3546/20A]

# 9.3 Program Results

S18CFF Example Program Results

X	Y	IFAIL
0.000E+00 5.000E+01 1.000E+00 3.000E+00 6.000E+01 1.000E+03	0.000E+00 1.564E-01 2.079E-01 1.968E-01 1.521E-01 1.213E-01 1.261E-02	0 0 0 0 0
-1.000E+00	-2.079E-01	0

[NP3546/20A] S18CFF.3 (last)