NAG Fortran Library Routine Document

D03PRF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D03PRF integrates a system of linear or nonlinear, first-order, time-dependent partial differential equations (PDEs) in one space variable, with scope for coupled ordinary differential equations (ODEs), and automatic adaptive spatial remeshing. The spatial discretisation is performed using the Keller box scheme (Keller (1970)) and the method of lines is employed to reduce the PDEs to a system of ODEs. The resulting system is solved using a Backward Differentiation Formula (BDF) method or a Theta method (switching between Newton's method and functional iteration).

2 Specification

SUBROUTINE D03PRF	(NPDE, TS, TOUT, PDEDEF, BNDARY, UVINIT, U, NPTS, X,
1	NLEFT, NCODE, ODEDEF, NXI, XI, NEQN, RTOL, ATOL, ITOL,
2	NORM, LAOPT, ALGOPT, REMESH, NXFIX, XFIX, NRMESH,
3	DXMESH, TRMESH, IPMINF, XRATIO, CONST, MONITF, W, NW,
4	IW, NIW, ITASK, ITRACE, IND, IFAIL)
INTEGER	NPDE, NPTS, NLEFT, NCODE, NXI, NEQN, ITOL, NXFIX,
1	NRMESH, IPMINF, NW, IW(NIW), NIW, ITASK, ITRACE, IND,
2	IFAIL
real	TS, TOUT, U(NEQN), X(NPTS), XI(*), RTOL(*), ATOL(*),
1	ALGOPT(30), XFIX(*), DXMESH, TRMESH, XRATIO, CONST,
2	W(NW)
LOGICAL	REMESH
CHARACTER*1	NORM, LAOPT
EXTERNAL	PDEDEF, BNDARY, UVINIT, ODEDEF, MONITF

3 Description

D03PRF integrates the system of first-order PDEs and coupled ODEs given by the master equations:

$$G_i(x, t, U, U_x, U_t, V, V) = 0, \quad i = 1, 2, \dots, \text{NPDE}, \ a \le x \le b, \ t \ge t_0,$$
 (1)

$$F_i(t, V, \dot{V}, \xi, U^*, U^*_x, U^*_t) = 0, \quad i = 1, 2, \dots, \text{NCODE}.$$
 (2)

In the PDE part of the problem given by (1), the functions G_i must have the general form

$$G_i = \sum_{j=1}^{\text{NPDE}} P_{i,j} \frac{\partial U_j}{\partial t} + \sum_{j=1}^{\text{NCODE}} Q_{i,j} \dot{V}_j + R_i = 0, \ i = 1, 2, \dots, \text{NPDE},$$
(3)

where $P_{i,j}$, $Q_{i,j}$ and R_i depend on x, t, U, U_x and V.

The vector U is the set of PDE solution values

$$U(x,t) = [U_1(x,t),\ldots,U_{\text{NPDE}}(x,t)]^T,$$

and the vector U_x is the partial derivative with respect to x. The vector V is the set of ODE solution values

 $V(t) = [V_1(t), \dots, V_{\text{NCODE}}(t)]^T,$

and \dot{V} denotes its derivative with respect to time.

In the ODE part given by (2), ξ represents a vector of n_{ξ} spatial coupling points at which the ODEs are coupled to the PDEs. These points may or may not be equal to some of the PDE spatial mesh points. U^* ,

 U_x^* and U_t^* are the functions U, U_x and U_t evaluated at these coupling points. Each F_i may only depend linearly on time derivatives. Hence equation (2) may be written more precisely as

$$F = A - B\dot{V} - CU_t^*,\tag{4}$$

where $\mathbf{F} = [F_1, \dots, F_{\text{NCODE}}]^T$, A is a vector of length NCODE, B is an NCODE by NCODE matrix, C is an NCODE by $(n_{\xi} \times \text{NPDE})$ matrix and the entries in A, B and C may depend on t, ξ , U^* , U^*_x and V. In practice the user only needs to supply a vector of information to define the ODEs and not the matrices B and C. (See Section 5 for the specification of the user-supplied subroutine ODEDEF.)

The integration in time is from t_0 to t_{out} , over the space interval $a \le x \le b$, where $a = x_1$ and $b = x_{NPTS}$ are the leftmost and rightmost points of a mesh $x_1, x_2, \ldots, x_{NPTS}$ defined initially by the user and (possibly) adapted automatically during the integration according to user-specified criteria.

The PDE system which is defined by the functions G_i must be specified in the user-supplied subroutine PDEDEF.

The initial $(t = t_0)$ values of the functions U(x, t) and V(t) must be specified in a subroutine UVINIT supplied by the user. Note that UVINIT will be called again following any remeshing, and so $U(x, t_0)$ should be specified for **all** values of x in the interval $a \le x \le b$, and not just the initial mesh points.

For a first-order system of PDEs, only one boundary condition is required for each PDE component U_i . The NPDE boundary conditions are separated into NLEFT at the left-hand boundary x = a, and NRIGHT at the right-hand boundary x = b, such that NLEFT + NRIGHT = NPDE. The position of the boundary condition for each component should be chosen with care; the general rule is that if the characteristic direction of U_i at the left-hand boundary (say) points into the interior of the solution domain, then the boundary condition for U_i should be specified at the left-hand boundary. Incorrect positioning of boundary conditions generally results in initialisation or integration difficulties in the underlying time integration routines.

The boundary conditions have the master equation form:

$$G_i^L(x, t, U, U_t, V, V) = 0$$
 at $x = a, \quad i = 1, 2, \dots, \text{NLEFT},$ (5)

at the left-hand boundary, and

$$G_i^R(x, t, U, U_t, V, \dot{V}) = 0 \text{ at } x = b, \quad i = 1, 2, \dots, \text{NRIGHT},$$
(6)

at the right-hand boundary.

Note that the functions G_i^L and G_i^R must not depend on U_x , since spatial derivatives are not determined explicitly in the Keller box scheme routines. If the problem involves derivative (Neumann) boundary conditions then it is generally possible to restate such boundary conditions in terms of permissible variables. Also note that G_i^L and G_i^R must be linear with respect to time derivatives, so that the boundary conditions have the general form:

$$\sum_{j=1}^{\text{NPDE}} E_{i,j}^L \frac{\partial U_j}{\partial t} + \sum_{j=1}^{\text{NCODE}} H_{i,j}^L \dot{V}_j + S_i^L = 0, \quad i = 1, 2, \dots, \text{NLEFT},$$
(7)

at the left-hand boundary, and

$$\sum_{j=1}^{\text{NPDE}} E_{i,j}^R \frac{\partial U_j}{\partial t} + \sum_{j=1}^{\text{NCODE}} H_{i,j}^R \dot{V}_j + S_i^R = 0, \quad i = 1, 2, \dots, \text{NRIGHT},$$
(8)

at the right-hand boundary, where $E_{i,j}^L$, $E_{i,j}^R$, $H_{i,j}^L$, $H_{i,j}^R$, S_i^L and S_i^R depend on x, t, U and V only. The boundary conditions must be specified in a subroutine BNDARY provided by the user.

The boundary conditions must be specified in a subfourne DIVDART provided by

The problem is subject to the following restrictions:

- (i) $P_{i,j}$, $Q_{i,j}$ and R_i must not depend on any time derivatives;
- (ii) $t_0 < t_{out}$, so that integration is in the forward direction;

- (iii) The evaluation of the function G_i is done approximately at the mid-points of the mesh X(i), for i = 1, 2, ..., NPTS, by calling the routine PDEDEF for each mid-point in turn. Any discontinuities in the function **must** therefore be at one or more of the fixed mesh points specified by XFIX;
- (iv) At least one of the functions $P_{i,j}$ must be non-zero so that there is a time derivative present in the PDE problem;

The algebraic-differential equation system which is defined by the functions F_i must be specified in the user-supplied subroutine ODEDEF. The user must also specify the coupling points ξ in the array XI.

The first-order equations are approximated by a system of ODEs in time for the values of U_i at mesh points. In this method of lines approach the Keller box scheme is applied to each PDE in the space variable only, resulting in a system of ODEs in time for the values of U_i at each mesh point. In total there are NPDE \times NPTS + NCODE ODEs in time direction. This system is then integrated forwards in time using a Backward Differentiation Formula (BDF) or a Theta method.

The adaptive space remeshing can be used to generate meshes that automatically follow the changing timedependent nature of the solution, generally resulting in a more efficient and accurate solution using fewer mesh points than may be necessary with a fixed uniform or non-uniform mesh. Problems with travelling wavefronts or variable-width boundary layers for example will benefit from using a moving adaptive mesh. The discrete time-step method used here (developed by Furzeland (1984)) automatically creates a new mesh based on the current solution profile at certain time-steps, and the solution is then interpolated onto the new mesh and the integration continues.

The method requires the user to supply a subroutine MONITF which specifies in an analytic or numeric form the particular aspect of the solution behaviour the user wishes to track. This so-called monitor function is used by the routines to choose a mesh which equally distributes the integral of the monitor function over the domain. A typical choice of monitor function is the second space derivative of the solution value at each point (or some combination of the second space derivatives if more than one solution component), which results in refinement in regions where the solution gradient is changing most rapidly.

The user specifies the frequency of mesh updates along with certain other criteria such as adjacent mesh ratios. Remeshing can be expensive and the user is encouraged to experiment with the different options in order to achieve an efficient solution which adequately tracks the desired features of the solution.

Note that unless the monitor function for the initial solution values is zero at all user-specified initial mesh points, a new initial mesh is calculated and adopted according to the user-specified remeshing criteria. The subroutine UVINIT will then be called again to determine the initial solution values at the new mesh points (there is no interpolation at this stage) and the integration proceeds.

4 References

Berzins M (1990) Developments in the NAG Library software for parabolic equations *Scientific Software Systems* (ed J C Mason and M G Cox) 59–72 Chapman and Hall

Berzins M, Dew P M and Furzeland R M (1989) Developing software for time-dependent problems using the method of lines and differential-algebraic integrators *Appl. Numer. Math.* **5** 375–397

Berzins M and Furzeland R M (1992) An adaptive theta method for the solution of stiff and nonstiff differential equations *Appl. Numer. Math.* **9** 1–19

Furzeland R M (1984) The construction of adaptive space meshes *TNER.85.022* Thornton Research Centre, Chester

Keller H B (1970) A new difference scheme for parabolic problems *Numerical Solutions of Partial Differential Equations* (ed J Bramble) **2** 327–350 Academic Press

Pennington S V and Berzins M (1994) New NAG Library software for first-order partial differential equations ACM Trans. Math. Softw. 20 63–99

Input

5 Parameters 1: NPDE - INTEGER Input On entry: the number of PDEs to be solved. Constraint: NPDE ≥ 1. 2: TS - real Input/Output On entry: the initial value of the independent variable t. Constraint: TS < TOUT. On exit: the value of t corresponding to the solution values in U. Normally TS = TOUT.

3: TOUT – *real*

On entry: the final value of t to which the integration is to be carried out.

4: PDEDEF – SUBROUTINE, supplied by the user. *External Procedure*

On entry: PDEDEF must evaluate the functions G_i which define the system of PDEs. PDEDEF is called approximately midway between each pair of mesh points in turn by D03PRF. Its specification is:

SUBROUTINE PDEDEF(NPDE, T, X, U, UDOT, UX, NCODE, V, VDOT, RES, 1 IRES) NPDE, NCODE, IRES INTEGER T, X, U(NPDE), UDOT(NPDE), UX(NPDE), V(*), real 1 VDOT(*), RES(NPDE) NPDE – INTEGER Input 1: On entry: the number of PDEs in the system. T – real 2: Input On entry: the current value of the independent variable t. 3: X – real Input On entry: the current value of the space variable x. U(NPDE) - real array Input 4: On entry: U(i) contains the value of the component $U_i(x,t)$, for i = 1, 2, ..., NPDE. 5: UDOT(NPDE) - real array Input On entry: UDOT(i) contains the value of the component $\frac{\partial U_i(x,t)}{\partial t}$, for $i = 1, 2, \dots$, NPDE. 6: UX(NPDE) - real array Input On entry: UX(i) contains the value of the component $\frac{\partial U_i(x,t)}{\partial x}$, for i = 1, 2, ..., NPDE. 7: NCODE - INTEGER Input On entry: the number of coupled ODEs in the system. 8: V(*) - real array Input On entry: V(i) contains the value of component $V_i(t)$, for i = 1, 2, ..., NCODE.

D03PRF

9: VDOT(*) – *real* array

On entry: VDOT(i) contains the value of component $\dot{\mathbf{V}}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.

10: RES(NPDE) – *real* array

On exit: RES(i) must contain the *i*th component of G, for i = 1, 2, ..., NPDE, where G is defined as

$$G_{i} = \sum_{j=1}^{\text{NPDE}} P_{i,j} \frac{\partial U_{j}}{\partial t} + \sum_{j=1}^{\text{NCODE}} Q_{i,j} \dot{V}_{j}, \qquad (9)$$

i.e., only terms depending explicitly on time derivatives, or

$$G_i = \sum_{j=1}^{\text{NPDE}} P_{i,j} \frac{\partial U_j}{\partial t} + \sum_{j=1}^{\text{NCODE}} Q_{i,j} \dot{V}_j + R_i,$$
(10)

i.e., all terms in equation (3).

The definition of G is determined by the input value of IRES.

11: IRES – INTEGER

Input/Output

On entry: the form of G_i that must be returned in the array RES. If IRES = -1, then equation (9) above must be used. If IRES = 1, then equation (10) above must be used.

On exit: should usually remain unchanged. However, the user may set IRES to force the integration routine to take certain actions, as described below:

IRES = 2

indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator (IFAIL) set to 6.

IRES = 3

indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PRF returns to the calling (sub)program with the error indicator (IFAIL) set to 4.

PDEDEF must be declared as EXTERNAL in the (sub)program from which D03PRF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

5: BNDARY – SUBROUTINE, supplied by the user.

External Procedure

BNDARY must evaluate the functions G_i^L and G_i^R which describe the boundary conditions, as given in (5) and (6).

Its specification is:

```
      SUBROUTINE BNDARY (NPDE, T, IBND, NOBC, U, UDOT, NCODE, V, VDOT, RES, IRES)

      INTEGER
      NPDE, IBND, NOBC, NCODE, IRES

      real
      T, U(NPDE), UDOT(NPDE), V(*), VDOT(*), RES(NOBC)

      1:
      NPDE - INTEGER
      Input

      On entry: the number of PDEs in the system.
      Input

      2:
      T - real
      Input

      On entry: the current value of the independent variable t.
      Input
```

Output

3: IBND - INTEGER Input On entry: specifies which boundary conditions are to be evaluated. If IBND = 0, then BNDARY must compute the left-hand boundary condition at x = a. If IBND $\neq 0$, then BNDARY must compute of the right-hand boundary condition at x = b. 4: NOBC - INTEGER Input On entry: NOBC specifies the number of boundary conditions at the boundary specified by IBND. 5: U(NPDE) - real array Input On entry: U(i) contains the value of the component $U_i(x,t)$ at the boundary specified by IBND, for $i = 1, 2, \ldots$, NPDE. 6: UDOT(NPDE) - real array Input On entry: U(i) contains the value of the component $\frac{\partial U_i(x,t)}{\partial t}$, for $i = 1, 2, \dots$, NPDE. 7: NCODE – INTEGER Input On entry: the number of coupled ODEs in the system. V(*) - real array 8: Input On entry: V(i) contains the value of component $V_i(t)$, for i = 1, 2, ..., NCODE. 9: VDOT(*) - real array Input On entry: VDOT(i) contains the value of component $V_i(t)$, for i = 1, 2, ..., NCODE. Note: VDOT(i), for i = 1, 2, ..., NCODE, may only appear linearly as in (11) and (12). 10: RES(NOBC) - real array Output On exit: RES(i) must contain the *i*th component of G^L or G^R , depending on the value of IBND, for i = 1, 2, ..., NOBC, where G^L is defined as $G_i^L = \sum_{i=1}^{\text{NPDE}} E_{i,j}^L \frac{\partial U_j}{\partial t} + \sum_{i=1}^{\text{NCODE}} H_{i,j}^L \dot{V}_j,$ (11)i.e., only terms depending explicitly on time derivatives, or $G_i^L = \sum_{j=1}^{\text{NPDE}} E_{i,j}^L \frac{\partial U_j}{\partial t} + \sum_{j=1}^{\text{NCODE}} H_{i,j}^L \dot{V}_j + S_i^L,$ (12)i.e., all terms in equation (7), and similarly for G_i^R . The definitions of G^L and G^R are determined by the input value of IRES. **IRES – INTEGER** Input/Output 11: On entry: the form of G_i^L (or G_i^R) that must be returned in the array RES. If IRES = -1, then equation (11) above must be used. If IRES = 1, then equation (12) above must be used. On exit: should usually remain unchanged. However, the user may set IRES to force the integration routine to take certain actions as described below: IRES = 2indicates to the integrator that control should be passed back immediately to the

calling (sub)program with the error indicator (IFAIL) set to 6.

[NP3546/20A]

IRES = 3

indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PRF returns to the calling (sub)program with the error indicator (IFAIL) set to 4.

BNDARY must be declared as EXTERNAL in the (sub)program from which D03PRF is called. Parameters denoted as *Input* must **not** be changed by this procedure. UVINIT – SUBROUTINE, supplied by the user. *External Procedure*

6:

UVINIT must supply the initial $(t = t_0)$ values of U(x, t) and V(t) for all values of x in the interval [a, b].

Its specification is:

	SUBROUTINE UVINIT(NPDE, NPTS, NXI, X, XI, U, NCODE, V)INTEGERNPDE, NPTS, NXI, NCODErealX(NPTS), XI(*), U(NPDE, NPTS), V(*)
1:	NPDE – INTEGER Input
	On entry: the number of PDEs in the system.
2:	NPTS – INTEGER Input
	On entry: the number of mesh points in the interval $[a, b]$.
3:	NXI – INTEGER Input
	On entry: the number of ODE/PDE coupling points.
4:	X(NPTS) – <i>real</i> array Input
	On entry: the current mesh. $X(i)$ contains the value of x_i for $i = 1, 2,, NPTS$.
5:	XI(*) – <i>real</i> array Input
	On entry: XI(i) contains the ODE/PDE coupling point, ξ_i , for $1, 2,, NXI$.
6:	U(NPDE,NPTS) – <i>real</i> array Output
	On exit: $U(i, j)$ must contain the value of component $U_i(x_j, t_0)$ for $i = 1, 2,, NPDE$, $j = 1, 2,, NPTS$.
7:	NCODE – INTEGER Input
	On entry: the number of coupled ODEs in the system.
8:	V(*) – <i>real</i> array Output
	On exit: $V(i)$ must contain the value of component $V_i(t_0)$ for $i = 1, 2,, NCODE$.

UVINIT must be declared as EXTERNAL in the (sub)program from which D03PRF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

7: U(NEQN) – *real* array

Output

On exit: U(NPDE × (j - 1) + i) contains the computed solution $U_i(x_j, t)$, for i = 1, 2, ..., NPDE; j = 1, 2, ..., NPTS, and U(NPTS × NPDE + k) contains $V_k(t)$, for k = 1, 2, ..., NCODE, evaluated at t = TS. 8:

NPTS – INTEGER On entry: the number of mesh points in the interval [a, b].

Constraint: NPTS \geq 3.

9: X(NPTS) – *real* array

On entry: the initial mesh points in the space direction. X(1) must specify the left-hand boundary, a, and X(NPTS) must specify the right-hand boundary, b.

Constraint: $X(1) < X(2) < \ldots < X(NPTS)$.

On exit: the final values of the mesh points.

10: NLEFT – INTEGER

On entry: the number of boundary conditions at the left-hand mesh point X(1).

Constraint: $0 \leq \text{NLEFT} \leq \text{NPDE}$.

11: NCODE – INTEGER

On entry: the number of coupled ODE components.

Constraint: NCODE \geq 0.

12: ODEDEF – SUBROUTINE, supplied by the user.

ODEDEF must evaluate the functions F, which define the system of ODEs, as given in (4). If the user wishes to compute the solution of a system of PDEs only (i.e., NCODE = 0), ODEDEF must be the dummy routine D03PEK. (D03PEK is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details.)

Its specification is:

SUBROUTINE ODEDEF(NPDE, T, NCODE, V, VDOT, NXI, XI, UCP, UCPX, UCPT, 1 F, IRES) NPDE, NCODE, NXI, IRES INTEGER real T, V(*), VDOT(*), XI(*), UCP(NPDE,*), 1 UCPX(NPDE,*), UCPT(NPDE,*), F(*) NPDE – INTEGER 1: Input On entry: the number of PDEs in the system. T – real 2: Input On entry: the current value of the independent variable t. NCODE - INTEGER 3: Input On entry: the number of coupled ODEs in the system. V(*) - real array 4: Input On entry: V(i) contains the value of component $V_i(t)$, for i = 1, 2, ..., NCODE. 5: VDOT(*) - real array Input On entry: VDOT(i) contains the value of component $\dot{V}_i(t)$, for i = 1, 2, ..., NCODE. NXI - INTEGER 6: Input On entry: the number of ODE/PDE coupling points.

Input

Input/Output

Input

Input

External Procedure

D03PRF

XI(*) - real array Input 7: On entry: XI(i) contains the ODE/PDE coupling point, ξ_i , for i = 1, 2, ..., NXI. UCP(NPDE,*) - real array 8: Input On entry: UCP(i, j) contains the value of $U_i(x, t)$ at the coupling point $x = \xi_i$, for $i = 1, 2, \dots, NPDE; j = 1, 2, \dots, NXI.$ UCPX(NPDE,*) - real array 9: Input On entry: UCPX(i, j) contains the value of $\frac{\partial U_i(x,t)}{\partial x}$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}; j = 1, 2, \dots, \text{NXI}.$ UCPT(NPDE,*) - real array 10: Input On entry: UCPT(i, j) contains the value of $\frac{\partial U_i}{\partial t}$ at the coupling point $x = \xi_j$, for $i = 1, 2, \dots, \text{NPDE}; j = 1, 2, \dots, \text{NXI}.$ 11: F(*) - real array Output On exit: F(i) must contain the *i*th component of F, for i = 1, 2, ..., NCODE, where F is defined as $F = -B\dot{V} - CU_t^*,$ (13)that is, only terms depending explicitly on time derivatives, or $F = A - B\dot{V} - CU_t^*,$ (14)that is, all terms in equation (4). The definition of F is determined by the input value of IRES. 12: **IRES – INTEGER** Input/Output On entry: the form of F that must be returned in the array F. If IRES = -1, then equation (13) above must be used. If IRES = 1, then equation (14) above must be used. On exit: should usually remain unchanged. However, the user may reset IRES to force the integration routine to take certain actions, as described below: IRES = 2indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator (IFAIL) set to 6. IRES = 3indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PRF returns to the calling (sub)program with the error indicator (IFAIL) set to 4.

ODEDEF must be declared as EXTERNAL in the (sub)program from which D03PRF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

NXI - INTEGER 13:

On entry: the number of ODE/PDE coupling points.

Constraints:

NXI = 0 for NCODE = 0, NXI ≥ 0 for NCODE > 0.

Input

Input

Input

Input

14: XI(*) - *real* array

Note: the dimension of the array XI must be at least max(1, NXI). On entry: XI(i), i = 1, 2, ..., NXI, must be set to the ODE/PDE coupling points, ξ_i . Constraint: X(1) \leq XI(1) < XI(2) < ... < XI(NXI) \leq X(NPTS).

15: NEON – INTEGER

On entry: the number of ODEs in the time direction.

Constraint: $NEQN = NPDE \times NPTS + NCODE$.

16: RTOL(*) – *real* array

Note: the dimension of the array RTOL must be at least 1 if ITOL = 1 or 2 and at least NEQN if ITOL = 3 or 4.

On entry: the relative local error tolerance.

Constraint: $RTOL(i) \ge 0$ for all relevant *i*.

17: ATOL(*) – *real* array

Note: the dimension of the array ATOL must be at least 1 if ITOL = 1 or 3 and at least NEQN if ITOL = 2 or 4.

On entry: the absolute local error tolerance.

Constraints:

 $ATOL(i) \ge 0$ for all relevant *i*. Corresponding elements of RTOL and ATOL cannot both be 0.0.

18: ITOL – INTEGER

a value to indicate the form of the local error test. ITOL indicates to D03PRF whether to interpret either or both of RTOL or ATOL as a vector or scalar. The error test to be satisfied is $||e_i/w_i|| < 1.0$, where w_i is defined as follows:

On entry:

ITOL	RTOL	ATOL	w_i
1	scalar	scalar	$RTOL(1) \times U(i) + ATOL(1)$
2	scalar	vector	$RTOL(1) \times U(i) + ATOL(i)$
3	vector	scalar	$RTOL(i) \times U(i) + ATOL(1)$
4	vector	vector	$\operatorname{RTOL}(i) \times \operatorname{U}(i) + \operatorname{ATOL}(i)$

In the above, e_i denotes the estimated local error for the *i*th component of the coupled PDE/ODE system in time, U(i), for i = 1, 2, ..., NEQN.

The choice of norm used is defined by the parameter NORM, see below.

Constraint: $1 \leq \text{ITOL} \leq 4$.

19: NORM – CHARACTER*1

On entry: the type of norm to be used. Two options are available:

'M' – maximum norm.

'A' – averaged L_2 norm.

If $U_{\rm norm}$ denotes the norm of the vector U of length NEQN, then for the averaged L_2 norm

$$U_{\rm norm} = \sqrt{\frac{1}{\rm NEQN} \sum_{i=1}^{\rm NEQN} {({\rm U}(i)/w_i)^2}}, \label{eq:unorm}$$

Input

while for the maximum norm

$$U_{\rm norm} = \max |\mathbf{U}(i)/w_i|.$$

See the description of the ITOL parameter for the formulation of the weight vector w. Constraint: NORM = 'M' or 'A'.

20: LAOPT – CHARACTER*1

On entry: the type of matrix algebra required. The possible choices are:

'F' – full matrix routines to be used;

'B' - banded matrix routines to be used;

'S' - sparse matrix routines to be used.

Constraint: LAOPT = 'F', 'B' or 'S'.

Note: the user is recommended to use the banded option when no coupled ODEs are present (i.e., NCODE = 0).

21: ALGOPT(30) - *real* array

On entry: ALGOPT may be set to control various options available in the integrator. If the user wishes to employ all the default options, then ALGOPT(1) should be set to 0.0. Default values will also be used for any other elements of ALGOPT set to zero. The permissible values, default values, and meanings are as follows:

ALGOPT(1) selects the ODE integration method to be used. If ALGOPT(1) = 1.0, a BDF method is used and if ALGOPT(1) = 2.0, a Theta method is used.

The default value is ALGOPT(1) = 1.0.

If ALGOPT(1) = 2.0, then ALGOPT(i), for i = 2, 3, 4 are not used.

ALGOPT(2) specifies the maximum order of the BDF integration formula to be used. ALGOPT(2) may be 1.0, 2.0, 3.0, 4.0 or 5.0.

The default value is ALGOPT(2) = 5.0.

ALGOPT(3) specifies what method is to be used to solve the system of nonlinear equations arising on each step of the BDF method. If ALGOPT(3) = 1.0 a modified Newton iteration is used and if ALGOPT(3) = 2.0 a functional iteration method is used. If functional iteration is selected and the integrator encounters difficulty, then there is an automatic switch to the modified Newton iteration.

The default value is ALGOPT(3) = 1.0.

ALGOPT(4) specifies whether or not the Petzold error test is to be employed. The Petzold error test results in extra overhead but is more suitable when algebraic equations are present, such as $P_{i,j} = 0.0$, for j = 1, 2, ..., NPDE for some *i* or when there is no $\dot{V}_i(t)$ dependence in the coupled ODE system. If ALGOPT(4) = 1.0, then the Petzold test is used. If ALGOPT(4) = 2.0, then the Petzold test is not used.

The default value is ALGOPT(4) = 1.0.

If ALGOPT(1) = 1.0, then ALGOPT(i), for i = 5, 6, 7 are not used.

ALGOPT(5), specifies the value of Theta to be used in the Theta integration method.

 $0.51 \le ALGOPT(5) \le 0.99.$

The default value is ALGOPT(5) = 0.55.

ALGOPT(6) specifies what method is to be used to solve the system of nonlinear equations arising on each step of the Theta method. If ALGOPT(6) = 1.0, a modified Newton iteration is used and if ALGOPT(6) = 2.0, a functional iteration method is used.

The default value is ALGOPT(6) = 1.0.

D03PRF.11

Input

ALGOPT(7) specifies whether or not the integrator is allowed to switch automatically between modified Newton and functional iteration methods in order to be more efficient. If ALGOPT(7) = 1.0, then switching is allowed and if ALGOPT(7) = 2.0, then switching is not allowed.

The default value is ALGOPT(7) = 1.0.

ALGOPT(11) specifies a point in the time direction, t_{crit} , beyond which integration must not be attempted. The use of t_{crit} is described under the parameter ITASK. If ALGOPT(1) \neq 0.0, a value of 0.0 for ALGOPT(11), say, should be specified even if ITASK subsequently specifies that t_{crit} will not be used.

ALGOPT(12) specifies the minimum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(12) should be set to 0.0.

ALGOPT(13) specifies the maximum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(13) should be set to 0.0.

ALGOPT(14) specifies the initial step size to be attempted by the integrator. If ALGOPT(14) = 0.0, then the initial step size is calculated internally.

ALGOPT(15) specifies the maximum number of steps to be attempted by the integrator in any one call. If ALGOPT(15) = 0.0, then no limit is imposed.

ALGOPT(23) specifies what method is to be used to solve the nonlinear equations at the initial point to initialise the values of U, U_t , V and \dot{V} . If ALGOPT(23) = 1.0, a modified Newton iteration is used and if ALGOPT(23) = 2.0, functional iteration is used.

The default value is ALGOPT(23) = 1.0.

ALGOPT(29) and ALGOPT(30) are used only for the sparse matrix algebra option, i.e., LAOPT = S'.

ALGOPT(29) governs the choice of pivots during the decomposition of the first Jacobian matrix. It should lie in the range 0.0 < ALGOPT(29) < 1.0, with smaller values biasing the algorithm towards maintaining sparsity at the expense of numerical stability. If ALGOPT(29) lies outside this range then the default value is used. If the routines regard the Jacobian matrix as numerically singular then increasing ALGOPT(29) towards 1.0 may help, but at the cost of increased fill-in.

The default value is ALGOPT(29) = 0.1.

ALGOPT(30) is used as a relative pivot threshold during subsequent Jacobian decompositions (see ALGOPT(29)) below which an internal error is invoked. ALGOPT(30) must be greater than zero, otherwise the default value is used. If ALGOPT(30) is greater than 1.0 no check is made on the pivot size, and this may be a necessary option if the Jacobian is found to be numerically singular (see ALGOPT(29)).

The default value is ALGOPT(30) = 0.0001.

22: REMESH – LOGICAL

On entry: indicates whether or not spatial remeshing should be performed.

REMESH = .TRUE. indicates that spatial remeshing should be performed as specified.

REMESH = .FALSE. indicates that spatial remeshing should be suppressed.

Note: REMESH should **not** be changed between consecutive calls to D03PRF. Remeshing can be switched off or on at specified times by using appropriate values for the parameters NRMESH and TRMESH at each call.

23: NXFIX – INTEGER

On entry: the number of fixed mesh points.

Constraint: $0 \leq \text{NXFIX} \leq \text{NPTS} - 2$.

Note: the end-points X(1) and X(NPTS) are fixed automatically and hence should not be specified as fixed points.

Input

24: XFIX(*) – *real* array

Note: the dimension of the array XFIX must be at least max(1, NXFIX).

On entry: XFIX(i), i = 1, 2, ..., NXFIX, must contain the value of the x coordinate at the *i*th fixed mesh point.

Constraint: XFIX(i) < XFIX(i + 1), i = 1, 2, ..., NXFIX - 1, and each fixed mesh point must coincide with a user-supplied initial mesh point, that is XFIX(i) = X(j) for some j, $2 \le j \le NPTS - 1$.

Note: the positions of the fixed mesh points in the array X remain fixed during remeshing, and so the number of mesh points between adjacent fixed points (or between fixed points and end-points) does not change. The user should take this into account when choosing the initial mesh distribution.

25: NRMESH – INTEGER

On entry:

NRMESH < 0

indicates that a new mesh is adopted according to the parameter DXMESH below. The mesh is tested every |NRMESH| timesteps.

NRMESH = 0

indicates that remeshing should take place just once at the end of the first time step reached when t > TRMESH (see below).

NRMESH > 0

indicates that remeshing will take place every NRMESH time steps, with no testing using DXMESH.

Note: NRMESH may be changed between consecutive calls to D03PRF to give greater flexibility over the times of remeshing.

26: DXMESH – real

On entry: determines whether a new mesh is adopted when NRMESH is set less than zero. A possible new mesh is calculated at the end of every |NRMESH| time steps, but is adopted only if

$$x_i^{(\text{new})} > x_i^{(\text{old})} + \text{DXMESH} \times (x_{i+1}^{(\text{old})} - x_i^{(\text{old})}),$$

or

$$x_i^{(\text{new})} < x_i^{(\text{old})} - \text{DXMESH} \times (x_i^{(\text{old})} - x_{i-1}^{(\text{old})}).$$

DXMESH thus imposes a lower limit on the difference between one mesh and the next. *Constraint*: DXMESH > 0.0.

Constraint. DAMESH ≥ 0 .

27: TRMESH – *real*

On entry: specifies when remeshing will take place when NRMESH is set to zero. Remeshing will occur just once at the end of the first time step reached when t is greater than TRMESH.

Note: TRMESH may be changed between consecutive calls to D03PRF to force remeshing at several specified times.

28: IPMINF – INTEGER

On entry: the level of trace information regarding the adaptive remeshing. Details are directed to the current advisory message unit (see X04ABF).

IPMINF = 0

No trace information.

Input

Input

Input

Input

IPMINF = 1

Brief summary of mesh characteristics.

IPMINF = 2

More detailed information, including old and new mesh points, mesh sizes and monitor function values.

Constraint: $0 \leq \text{IPMINF} \leq 2$.

29: XRATIO – *real*

On entry: input bound on adjacent mesh ratio (greater than 1.0 and typically in the range 1.5 to 3.0). The resmeshing routines will attempt to ensure that

$$(x_i - x_{i-1})$$
/XRATIO < $x_{i+1} - x_i$ < XRATIO × $(x_i - x_{i-1})$

Suggested value: XRATIO = 1.5.

Constraint: XRATIO > 1.0.

30: CONST – *real*

On entry: an input bound on the sub-integral of the monitor function $F^{mon}(x)$ over each space step. The remeshing routines will attempt to ensure that

$$\int_{x_1}^{x_{i+1}} \mathcal{F}^{\text{mon}}(x) dx \leq \text{CONST} \int_{x_1}^{x_{\text{NPTS}}} F^{\text{mon}}(x) dx,$$

(see Furzeland (1984)). CONST gives the user more control over the mesh distribution e.g., decreasing CONST allows more clustering. A typical value is 2/(NPTS - 1), but the user is encouraged to experiment with different values. Its value is not critical and the mesh should be qualitatively correct for all values in the range given below.

Suggested value: CONST = 2.0/(NPTS - 1).

Constraint: $0.1/(\text{NPTS} - 1) \leq \text{CONST} \leq 10.0/(\text{NPTS} - 1)$.

31: MONITF – SUBROUTINE, supplied by the user.

External Procedure

MONITF must supply and evaluate a remesh monitor function to indicate the solution behaviour of interest.

If the user specifies REMESH = .FALSE., i.e., no remeshing, then MONITF will not be called and the dummy routine D03PEL may be used for MONITF. (D03PEL is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details.)

Its specification is:

	SUBROUTINE MONITF(T, NPTS, NPDE, X, U, FMON)INTEGERNPTS, NPDErealT, X(NPTS), U(NPDE,NPTS), FMON(NPTS)	
1:	T – <i>real</i>	Input
	On entry: the current value of the independent variable t .	
2:	NPTS – INTEGER	Input
	On entry: the number of mesh points in the interval $[a, b]$.	
3:	NPDE – INTEGER	Input
	On entry: the number of PDEs in the system.	

Input

D03PRF

Workspace

Input

4:	X(NPTS) – <i>real</i> array Input	
	On entry: the current mesh. $X(i)$ contains the value of x_i for $i = 1, 2,, NPTS$.	
5:	U(NPDE,NPTS) – <i>real</i> array Input	
	On entry: $U(i, j)$ contains the value of component $U_i(x, t)$ at $x = X(j)$ and time t, for $i = 1, 2,, NPDE$, $j = 1, 2,, NPTS$.	
6:	FMON(NPTS) – <i>real</i> array Output	
	On exit: FMON(i) must contain the value of the monitor function $F^{mon}(x)$ at mesh point $x = X(i)$.	
	Constraint: $FMON(i) \ge 0$.	

MONITF must be declared as EXTERNAL in the (sub)program from which D03PRF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

32: W(NW) – *real* array

33: NW – INTEGER

On entry: the dimension of the array W as declared in the (sub)program from which D03PRF is called. Its size depends on the type of matrix algebra selected:

LAOPT = 'F',

 $NW \ge NEQN \times NEQN + NEQN + NWKRES + LENODE,$

LAOPT = 'B',

 $NW \ge (2 \times ML + MU + 2) \times NEQN + NWKRES + LENODE,$

LAOPT = 'S',

 $NW \ge 4 \times NEQN + 11 \times NEQN/2 + 1 + NWKRES + LENODE,$

where ML and MU are the lower and upper half bandwidths, given by ML = NPDE + NLEFT - 1, $MU = 2 \times NPDE - NLEFT - 1$ for problems involving PDEs only, and ML = MU = NEQN - 1, for coupled PDE/ODE problems.

 $NWKRES = NPDE \times (3 \times NPDE + 6 \times NXI + NPTS + 15) + NXI + NCODE + 7 \times NPTS + NXFIX + 1 when NCODE > 0, and NXI > 0.$

NWKRES = NPDE \times (3 \times NPDE + NPTS + 21) + NCODE + 7 \times NPTS + NXFIX + 2

when NCODE > 0, and NXI = 0.

 $NWKRES = NPDE \times (3 \times NPDE + NPTS + 21) + 7 \times NPTS + NXFIX + 3$

when NCODE = 0.

 $LENODE = (6 + int(ALGOPT(2))) \times NEQN + 50$, when the BDF method is used and,

LENODE = $9 \times NEQN + 50$, when the Theta method is used.

Note: when using the sparse option, the value of NW may be too small when supplied to the integrator. An estimate of the minimum size of NW is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

34: IW(NIW) - INTEGER array

On exit: the following components of the array IW concern the efficiency of the integration.

IW(1) contains the number of steps taken in time.

IW(2) contains the number of residual evaluations of the resulting ODE system used. One such evaluation involves evaluating the PDE functions at all the mesh points, as well as one evaluation of the functions in the boundary conditions.

IW(3) contains the number of Jacobian evaluations performed by the time integrator.

Output

IW(4) contains the order of the ODE method last used in the time integration.

IW(5) contains the number of Newton iterations performed by the time integrator. Each iteration involves residual evaluation of the resulting ODE system followed by a back-substitution using the LU decomposition of the Jacobian matrix.

The rest of the array is used as workspace.

35: NIW – INTEGER

On entry: the dimension of the array IW as declared in the (sub)program from which D03PRF is called. Its size depends on the type of matrix algebra selected:

LAOPT = 'F',

NIW $\geq 25 + NXFIX$,

LAOPT = 'B',

 $NIW \ge NEQN + 25 + NXFIX,$

LAOPT = 'S',

NIW $\geq 25 \times NEQN + 25 + NXFIX.$

Note: when using the sparse option, the value of NIW may be too small when supplied to the integrator. An estimate of the minimum size of NIW is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

36: ITASK – INTEGER

On entry: the task to be performed by the ODE integrator. The permitted values of ITASK and their meanings are detailed below:

ITASK = 1

normal computation of output values U at t = TOUT (by overshooting and interpolating).

ITASK = 2

take one step in the time direction and return.

ITASK = 3

stop at first internal integration point at or beyond t = TOUT.

ITASK = 4

normal computation of output values U at t = TOUT but without overshooting $t = t_{\text{crit}}$, where t_{crit} is described under the parameter ALGOPT.

ITASK = 5

take one step in the time direction and return, without passing t_{crit} , where t_{crit} is described under the parameter ALGOPT.

Constraint: $1 \leq ITASK \leq 5$.

37: ITRACE – INTEGER

On entry: the level of trace information required from D03PRF and the underlying ODE solver as follows:

If ITRACE ≤ -1 , no output is generated.

If ITRACE = 0, only warning messages from the PDE solver are printed on the current error message unit (see X04AAF).

If ITRACE = 1, then output from the underlying ODE solver is printed on the current advisory message unit (see X04ABF). This output contains details of Jacobian entries, the nonlinear iteration and the time integration during the computation of the ODE system.

Input

Input

If ITRACE = 2, then the output from the underlying ODE solver is similar to that produced when ITRACE = 1, except that the advisory messages are given in greater detail.

If ITRACE \geq 3, then the output from the underlying ODE solver is similar to that produced when ITRACE = 2, except that the advisory messages are given in greater detail.

Users are advised to set ITRACE = 0, unless they are experienced with the sub-chapter D02M–N of the NAG Fortran Library.

38: IND – INTEGER

On entry: IND must be set to 0 or 1.

IND = 0

starts or restarts the integration in time.

IND = 1

continues the integration after an earlier exit from the routine. In this case, only the parameters TOUT and IFAIL and the remeshing parameters NRMESH, DXMESH, TRMESH, XRATIO and CONST may be reset between calls to D03PRF.

Constraint: $0 \leq IND \leq 1$.

On exit: IND = 1.

39: IFAIL – INTEGER

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry	r, (TOUT – TS) is too small,			
or	ITASK \neq 1, 2, 3, 4 or 5,			
or	at least one of the coupling points defined in array XI is outside the interval			
	[X(1),X(NPTS)],			
or	NPTS < 3 ,			
or	NPDE < 1,			
or	NLEFT not in the range 0 to NPDE,			
or	NORM \neq 'A' or 'M',			
or	LAOPT \neq 'F', 'B' or 'S',			
or	ITOL \neq 1, 2, 3 or 4,			
or	$IND \neq 0$ or 1,			
or	incorrectly defined user mesh, i.e., $X(i) \ge X(i+1)$ for some $i = 1, 2,, NPTS - 1$,			
or	NW or NIW are too small,			
or	NCODE and NXI are incorrectly defined,			
or	IND = 1 on initial entry to D03PRF,			
or	an element of RTOL or ATOL < 0.0 ,			
or	corresponding elements of RTOL and ATOL are both 0.0,			

Input/Output

Input/Output

points,

or	$NEQN \neq NPDE \times NPTS + NCODE$,
or	NXFIX not in the range 0 to NPTS -2 ,
or	fixed mesh point(s) do not coincide with any of the user-supplied mesh
or	DXMESH < 0.0,
or	IPMINF $\neq 0, 1$ or 2,
or	XRATIO ≤ 1.0 ,
or	CONST not in the range $0.1/(NPTS - 1)$ to $10/(NPTS - 1)$.

IFAIL = 2

The underlying ODE solver cannot make any further progress, with the values of ATOL and RTOL, across the integration range from the current point t = TS. The components of U contain the computed values at the current point t = TS.

IFAIL = 3

In the underlying ODE solver, there were repeated error test failures on an attempted step, before completing the requested task, but the integration was successful as far as t = TS. The problem may have a singularity, or the error requirement may be inappropriate. Incorrect positioning of boundary conditions may also result in this error.

IFAIL = 4

In setting up the ODE system, the internal initialisation routine was unable to initialise the derivative of the ODE system. This could be due to the fact that IRES was repeatedly set to 3 in one of the user-supplied subroutines PDEDEF, BNDARY or ODEDEF, when the residual in the underlying ODE solver was being evaluated. Incorrect positioning of boundary conditions may also result in this error.

IFAIL = 5

In solving the ODE system, a singular Jacobian has been encountered. The user should check their problem formulation.

IFAIL = 6

When evaluating the residual in solving the ODE system, IRES was set to 2 in one of the usersupplied subroutines PDEDEF, BNDARY or ODEDEF. Integration was successful as far as t = TS.

IFAIL = 7

The values of ATOL and RTOL are so small that the routine is unable to start the integration in time.

IFAIL = 8

In one of the user-supplied routines, PDEDEF, BNDARY or ODEDEF, IRES was set to an invalid value.

IFAIL = 9

A serious error has occurred in an internal call to D02NNF. Check problem specification an all parameters and array dimensions. Setting ITRACE = 1 may provide more information. If the problem persists, contact NAG.

IFAIL = 10

The required task has been completed, but it is estimated that a small change in ATOL and RTOL is unlikely to produce any change in the computed solution. (Only applies when the user is not operating in one step mode, that is when ITASK $\neq 2$ or 5.)

IFAIL = 11

An error occurred during Jacobian formulation of the ODE system (a more detailed error description may be directed to the current advisory message unit). If using the sparse matrix algebra option, the values of ALGOPT(29) and ALGOPT(30) may be inappropriate.

IFAIL = 12

In solving the ODE system, the maximum number of steps specified in ALGOPT(15) has been taken.

IFAIL = 13

Some error weights w_i became zero during the time integration (see description of ITOL). Pure relative error control (ATOL(i) = 0.0) was requested on a variable (the *i*th) which has become zero. The integration was succesful as far as t = TS.

IFAIL = 14

Not applicable.

IFAIL = 15

When using the sparse option, the value of NIW or NW was insufficient (more detailed information may be directed to the current error message unit).

IFAIL = 16

REMESH has been changed between calls to D03PRF.

7 Accuracy

The routine controls the accuracy of the integration in the time direction but not the accuracy of the approximation in space. The spatial accuracy depends on both the number of mesh points and on their distribution in space. In the time integration only the local error over a single step is controlled and so the accuracy over a number of steps cannot be guaranteed. The user should therefore test the effect of varying the accuracy parameters, ATOL and RTOL.

8 Further Comments

The Keller box scheme can be used to solve higher-order problems which have been reduced to first-order by the introduction of new variables (see the example in Section 9). In general, a second-order problem can be solved with slightly greater accuracy using the Keller box scheme instead of a finite-difference scheme (D03PPF for example), but at the expense of increased CPU time due to the larger number of function evaluations required.

It should be noted that the Keller box scheme, in common with other central-difference schemes, may be unsuitable for some hyperbolic first-order problems such as the apparently simple linear advection equation $U_t + aU_x = 0$, where a is a constant, resulting in spurious oscillations due to the lack of dissipation. This type of problem requires a discretisation scheme with upwind weighting (D03PSF for example), or the addition of a second-order artificial dissipation term.

The time taken by the routine depends on the complexity of the system, the accuracy requested, and the frequency of the mesh updates. For a given system with fixed accuracy and mesh-update frequency it is approximately proportional to NEQN.

9 Example

This example is the first-order system

$$\frac{\partial U_1}{\partial t} + \frac{\partial U_1}{\partial x} + \frac{\partial U_2}{\partial x} = 0,$$

$$\frac{\partial U_2}{\partial t} + 4 \frac{\partial U_1}{\partial x} + \frac{\partial U_2}{\partial x} = 0,$$

for $x \in [0,1]$ and $t \ge 0$.

The initial conditions are

$$U_1(x,0) = e^x,$$

 $U_2(x,0) = x^2 + \sin(2\pi x^2)$

and the Dirichlet boundary conditions for U_1 at x = 0 and U_2 at x = 1 are given by the exact solution:

$$U_{1}(x,t) = \frac{1}{2} \{ e^{x+t} + e^{x-3t} \} + \frac{1}{4} \{ \sin(2\pi(x-3t)^{2}) - \sin(2\pi(x+t)^{2}) \} + 2t^{2} - 2xt, U_{2}(x,t) = e^{x-3t} - e^{x+t} + \frac{1}{2} \{ \sin(2\pi(x-3t)^{2}) + \sin(2\pi(x+t)^{2}) \} + x^{2} + 5t^{2} - 2xt.$$

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
DO3PRF Example Program Text
*
*
      Mark 16 Release. NAG Copyright 1993.
*
      .. Parameters ..
      INTEGER
                        NOUT
      PARAMETER
                        (NOUT=6)
                        NPDE, NPTS, NV, NXI, NXFIX, NLEFT, NEQN, NIW, NWKRES, LENODE, NW, INTPTS, ITYPE
      TNTEGER
     +
                        (NPDE=2,NPTS=61,NV=0,NXI=0,NXFIX=0,NLEFT=1,
      PARAMETER
                        NEQN=NPDE*NPTS+NV,NIW=25+NXFIX,
     +
     +
                        NWKRES=NPDE*(NPTS+21+3*NPDE)+7*NPTS+NXFIX+3,
                        LENODE=11*NEQN+50,NW=NEQN*NEQN+NEQN+NWKRES+
     +
     +
                        LENODE, INTPTS=5, ITYPE=1)
*
      .. Scalars in Common ..
      real
                        Ρ
      .. Local Scalars ..
*
                        CONST, DXMESH, TOUT, TRMESH, TS, XRATIO, XX
      real
                        I, IFAIL, IND, IPMINF, IT, ITASK, ITOL, ITRACE,
      TNTEGER
                       NRMESH
     +
                       REMESH, THETA
      LOGICAL
                        LAOPT, NORM
      CHARACTER
      .. Local Arrays ..
*
                        ALGOPT(30), ATOL(1), RTOL(1), U(NPDE, NPTS),
      real
                        UE(NPDE,NPTS), UOUT(NPDE,INTPTS,ITYPE), W(NW),
     +
     +
                        X(NPTS), XFIX(1), XI(1), XOUT(INTPTS)
      INTEGER
                        IW(NIW)
      .. External Functions ..
*
                XO1AAF
      real
      EXTERNAL
                        X01AAF
      .. External Subroutines ..
EXTERNAL BNDARY, DO3PEK, DO3PRF, DO3PZF, EXACT, MONITF,
      EXTERNAL
     +
                        PDEDEF, UVINIT
      .. Common blocks ..
*
                        /PI/P
      COMMON
      .. Executable Statements ..
*
      WRITE (NOUT, *) 'DO3PRF Example Program Results'
      P = XO1AAF(XX)
      ITRACE = 0
      ITOL = 1
      ATOL(1) = 0.5e-4
      RTOL(1) = ATOL(1)
      WRITE (NOUT, 99996) ATOL, NPTS
*
*
      Set remesh parameters ..
      REMESH = .TRUE.
      NRMESH = 3
```

```
DXMESH = 0.0e^{0}
      CONST = 5.0e0/(NPTS-1.0e0)
      XRATIO = 1.2e0
      IPMINF = 0
      WRITE (NOUT, 99999) NRMESH
*
*
      Initialise mesh ..
      DO 20 I = 1, NPTS
         X(I) = (I-1.0e^{0}) / (NPTS-1.0e^{0})
   20 CONTINUE
*
      XOUT(1) = 0.0e0
      XOUT(2) = 0.25e0
      XOUT(3) = 0.5e0
      XOUT(4) = 0.75e0
      XOUT(5) = 1.0e0
      WRITE (NOUT, 99998) (XOUT(I), I=1, INTPTS)
*
      XI(1) = 0.0e0
      NORM = 'A'
      LAOPT = 'F'
      IND = 0
      ITASK = 1
*
      Set THETA to .TRUE. if the Theta integrator is required
*
      THETA = .FALSE.
      DO 40 I = 1, 30
ALGOPT(I) = 0.0e0
   40 CONTINUE
      IF (THETA) THEN
         ALGOPT(1) = 2.0e0
         ALGOPT(6) = 2.0e0
         ALGOPT(7) = 1.0e0
      END IF
      Loop over output value of t
*
*
      TS = 0.0e0
      TOUT = 0.0e0
*
      DO 60 IT = 1, 5
         TOUT = 0.05e0 \times IT
         IFAIL = 0
*
         CALL D03PRF(NPDE,TS,TOUT,PDEDEF,BNDARY,UVINIT,U,NPTS,X,NLEFT,
     +
                      NV, DO3PEK, NXI, XI, NEQN, RTOL, ATOL, ITOL, NORM, LAOPT,
     +
                      ALGOPT, REMESH, NXFIX, XFIX, NRMESH, DXMESH, TRMESH,
     +
                      IPMINF, XRATIO, CONST, MONITF, W, NW, IW, NIW, ITASK,
     +
                      ITRACE, IND, IFAIL)
*
*
         Interpolate at output points ...
         CALL D03PZF(NPDE,0,U,NPTS,X,XOUT,INTPTS,ITYPE,UOUT,IFAIL)
         Check against exact solution ..
         CALL EXACT(TS,NPDE, INTPTS, XOUT, UE)
*
         WRITE (NOUT,99997) TS
         WRITE (NOUT,99994) (UOUT(1,1,1),I=1,INTPTS)
         WRITE (NOUT, 99993) (UE(1,I), I=1, INTPTS)
         WRITE (NOUT,99992) (UOUT(2,I,1),I=1,INTPTS)
         WRITE (NOUT, 99991) (UE(2,1), I=1, INTPTS)
   60 CONTINUE
      WRITE (NOUT, 99995) IW(1), IW(2), IW(3), IW(5)
      STOP
*
99999 FORMAT (' Remeshing every ',I3,' time steps',/)
99998 FORMAT (′ X
                           ',5F10.4,/)
99997 FORMAT (' T = ', F6.3)
99996 FORMAT (//' Accuracy requirement =', e10.3, ' Number of points = ',
```

```
I3,/)
99995 FORMAT (' Number of integration steps in time = ',I6,/' Number o',
             'f function evaluations = ',I6,/' Number of Jacobian eval',
    +
     ^{+}
             'uations =',I6,/' Number of iterations = ',I6,/)
99994 FORMAT (' Approx U1', 5F10.4)
99993 FORMAT (' Exact U1',5F10.4)
99992 FORMAT (' Approx U2',5F10.4)
99991 FORMAT (' Exact U2',5F10.4,/)
      END
*
      SUBROUTINE UVINIT(NPDE, NPTS, NXI, X, XI, U, NV, V)
*
      .. Scalar Arguments ..
      INTEGER
                        NPDE, NPTS, NV, NXI
      .. Array Arguments ..
*
                         U(NPDE, NPTS), V(*), X(NPTS), XI(*)
      real
      .. Scalars in Common ..
*
      real
                         Ρ
      .. Local Scalars ..
4
      INTEGER
                         Τ
      .. Intrinsic Functions ..
*
      INTRINSIC EXP, SIN
      .. Common blocks ..
*
                         /PI/P
      COMMON
      .. Executable Statements ..
      DO 20 I = 1, NPTS
         U(1,I) = EXP(X(I))
         U(2,I) = X(I) * *2 + SIN(2.0e0*P*X(I)**2)
   20 CONTINUE
      RETURN
      END
*
      SUBROUTINE PDEDEF (NPDE, T, X, U, UDOT, DUDX, NV, V, VDOT, RES, IRES)
      .. Scalar Arguments ..
*
      real
                         т, х
                         IRES, NPDE, NV
      INTEGER
      .. Array Arguments ..
                         DUDX(NPDE), RES(NPDE), U(NPDE), UDOT(NPDE),
      real
     +
                         V(*), VDOT(*)
      .. Executable Statements ..
*
      IF (IRES.EQ.-1) THEN
         RES(1) = UDOT(1)
         RES(2) = UDOT(2)
      ELSE
         RES(1) = UDOT(1) + DUDX(1) + DUDX(2)
         RES(2) = UDOT(2) + 4.0e0 * DUDX(1) + DUDX(2)
      END IF
      RETURN
      END
*
      SUBROUTINE BNDARY(NPDE, T, IBND, NOBC, U, UDOT, NV, V, VDOT, RES, IRES)
      .. Scalar Arguments ..
4
      real
                         Т
      INTEGER
                         IBND, IRES, NOBC, NPDE, NV
      .. Array Arguments ..
      real
                         RES(NOBC), U(NPDE), UDOT(NPDE), V(*), VDOT(*)
      .. Scalars in Common ..
*
      real
                         Ρ
      .. Local Scalars ..
*
      real
                         ΡP
      .. Intrinsic Functions ..
*
      INTRINSIC
                        EXP, SIN
      .. Common blocks ..
      COMMON
                         /PI/P
      .. Executable Statements ..
      PP = 2.0e0*P
      IF (IBND.EQ.0) THEN
         IF (IRES.EQ.-1) THEN
            \operatorname{RES}(1) = 0.0 \boldsymbol{e}0
         ELSE
            RES(1) = U(1) - 0.5e0 * (EXP(T) + EXP(-3.0e0 * T)) -
     +
                      0.25e0*(SIN(PP*9.0e0*T**2)-SIN(PP*T**2)) -
```

```
2.0e0*T**2
     +
         END IF
     ELSE
         IF (IRES.EQ.-1) THEN
            RES(1) = 0.0e0
         ELSE
            RES(1) = U(2) - (EXP(1.0e0-3.0e0*T)-EXP(1.0e0+T)
                     +0.5e0*(SIN(PP*(1.0e0-3.0e0*T)**2)+SIN(PP*(1.0e0+T)
     +
     +
                     **2))+1.0e0+5.0e0*T**2-2.0e0*T)
        END IF
     END IF
     RETURN
      END
*
      SUBROUTINE EXACT(T,NPDE,NPTS,X,U)
*
     Exact solution (for comparison purposes)
      .. Scalar Arguments ..
     real
                       т
      INTEGER
                       NPDE, NPTS
      .. Array Arguments ..
*
     real
                       U(NPDE,NPTS), X(NPTS)
*
      .. Scalars in Common ..
     real
                       Ρ
      .. Local Scalars ..
     real
                       PP
      INTEGER
                       Τ
      .. Intrinsic Functions ..
      INTRINSIC EXP, SIN
*
      .. Common blocks ..
                       /PI/P
      COMMON
*
      .. Executable Statements ..
     PP = 2.0e0 * P
     DO 20 I = 1, NPTS
         U(1,I) = 0.5e^{0*}(EXP(X(I)+T)+EXP(X(I)-3.0e^{0*T})) +
                  0.25e0*(SIN(PP*(X(I)-3.0e0*T)**2)-SIN(PP*(X(I)+T)**2))
     +
                  + 2.0e0*T**2 - 2.0e0*X(I)*T
     +
         U(2,I) = EXP(X(I)-3.0e0*T) - EXP(X(I)+T) + 0.5e0*(SIN(PP*(X(I))))
     +
                  -3.0e0*T)**2+SIN(PP*(X(I)+T)**2)) + X(I)**2 +
                  5.0e0*T**2 - 2.0e0*X(I)*T
     +
  20 CONTINUE
     RETURN
     END
*
      SUBROUTINE MONITF(T,NPTS,NPDE,X,U,FMON)
      .. Scalar Arguments ..
      real
                         Т
      INTEGER
                        NPDE, NPTS
      .. Array Arguments ..
*
                        FMON(NPTS), U(NPDE,NPTS), X(NPTS)
      real
      .. Local Scalars
                        •
     real
                        D2X1, D2X2, H1, H2, H3
      TNTEGER
                        Т
      .. Intrinsic Functions ..
      INTRINSIC
                        ABS. MAX
      .. Executable Statements ..
     DO 20 I = 2, NPTS - 1
         H1 = X(I) - X(I-1)
         H2 = X(I+1) - X(I)
         H3 = 0.5e0 * (X(I+1) - X(I-1))
         Second derivatives ...
*
         D2X1 = ABS(((U(1,I+1)-U(1,I))/H2-(U(1,I)-U(1,I-1))/H1)/H3)
         D2X2 = ABS(((U(2,I+1)-U(2,I))/H2-(U(2,I)-U(2,I-1))/H1)/H3)
         FMON(I) = MAX(D2X1, D2X2)
  20 CONTINUE
      FMON(1) = FMON(2)
      FMON(NPTS) = FMON(NPTS-1)
      RETURN
     END
```

9.2 Program Data

None.

9.3 Program Results

DO3PRF Example Program Results

Accuracy requirement = 0.500E-04 Number of points = 61

Remeshing every 3 time steps

Х	0.0000	0.2500	0.5000	0.7500	1.0000
T = 0.050 Approx U1 Exact U1 Approx U2 Exact U2	0.9923 0.9923 -0.0997 -0.0998	1.0894 1.0893 0.1057 0.1046	1.4686 1.4686 0.7180 0.7193	2.3388 2.3391 0.0967 0.0966	2.1071 2.1073 0.2021 0.2022
T = 0.100 Approx U1 Exact U1 Approx U2 Exact U2	1.0613 1.0613 -0.0150 -0.0150	0.9856 0.9851 -0.0481 -0.0495	1.3120 1.3113 0.1075 0.1089	2.3084 2.3092 -0.3240 -0.3235	2.1039 2.1025 0.3753 0.3753
T = 0.150 Approx U1 Exact U1 Approx U2 Exact U2	1.1485 1.1485 0.1370 0.1366	0.9763 0.9764 -0.0250 -0.0266	1.2658 1.2654 -0.4107 -0.4100	2.0906 2.0911 -0.8577 -0.8567	2.2027 2.2027 0.3096 0.3096
T = 0.200 Approx U1 Exact U1 Approx U2 Exact U2	1.0956 1.0956 0.0381 0.0370	1.0529 1.0515 0.1282 0.1247	1.3407 1.3393 -0.7979 -0.7961	1.8322 1.8327 -1.1776 -1.1784	2.2035 2.2050 -0.4221 -0.4221
T = 0.250 Approx U1 Exact U1 Approx U2 Exact U2	0.8119 0.8119 -0.4968 -0.4992	1.1288 1.1276 0.2123 0.2078	1.5163 1.5142 -1.0259 -1.0257	1.6076 1.6091 -1.2149 -1.2183	2.2027 2.2035 -1.3938 -1.3938
Number of i Number of f Number of J Number of i	Eunction ev Jacobian ev	aluations aluations	= 2579	50	