NAG Fortran Library Routine Document F08NJF (SGEBAK/DGEBAK)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

F08NJF (SGEBAK/DGEBAK) transforms eigenvectors of a balanced matrix to those of the original real nonsymmetric matrix.

2 Specification

```
SUBROUTINE FO8NJF(JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)
ENTRY sgebak (JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)

INTEGER N, ILO, IHI, M, LDV, INFO

real SCALE(*), V(LDV,*)

CHARACTER*1 JOB, SIDE
```

The ENTRY statement enables the routine to be called by its LAPACK name.

3 Description

This routine is intended to be used after a real nonsymmetric matrix A has been balanced by F08NHF (SGEBAL/DGEBAL), and eigenvectors of the balanced matrix A_{22}'' have subsequently been computed.

For a description of balancing, see the document for F08NHF (SGEBAL/DGEBAL). The balanced matrix A'' is obtained as $A'' = DPAP^TD^{-1}$, where P is a permutation matrix and D is a diagonal scaling matrix. This routine transforms left or right eigenvectors as follows:

```
if x is a right eigenvector of A'', P^TD^{-1}x is a right eigenvector of A; if y is a left eigenvector of A'', P^TDy is a left eigenvector of A.
```

4 References

None.

5 Parameters

1: JOB – CHARACTER*1

Input

On entry: this **must** be the same parameter JOB as supplied to F08NHF (SGEBAL/DGEBAL). Constraint: JOB = 'N', 'P', 'S' or 'B'.

2: SIDE – CHARACTER*1

Input

On entry: indicates whether left or right eigenvectors are to be transformed, as follows:

```
if SIDE = 'L', left eigenvectors are transformed;
if SIDE = 'R', right eigenvectors are transformed.
```

Constraint: SIDE = 'L' or 'R'.

3: N – INTEGER

Input

On entry: n, the number of rows of the matrix of eigenvectors.

Constraint: $N \ge 0$.

4: ILO – INTEGER 5: IHI – INTEGER Input

On entry: the values i_{lo} and i_{hi} , as returned by F08NHF (SGEBAL/DGEBAL).

Constraints:

 $1 \le ILO \le IHI \le N$ if N > 0, ILO = 1 and IHI = 0 if N = 0.

6: SCALE(*) – *real* array

Input

Note: the dimension of the array SCALE must be at least max(1, N).

On entry: details of the permutations and/or the scaling factors used to balance the original real nonsymmetric matrix, as returned by F08NHF (SGEBAL/DGEBAL).

7: M - INTEGER

On entry: m, the number of columns of the matrix of eigenvectors.

Constraint: M > 0.

8: V(LDV,*) - real array

Input/Output

Note: the second dimension of the array V must be at least max(1, M).

On entry: the matrix of left or right eigenvectors to be transformed.

On exit: the transformed eigenvectors.

9: LDV – INTEGER Input

On entry: the first dimension of the array V as declared in the (sub)program from which F08NJF (SGEBAK/DGEBAK) is called.

Constraint: LDV $\geq \max(1, N)$.

10: INFO – INTEGER Output

On exit: INFO = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

INFO < 0

If INFO = -i, the *i*th parameter had an illegal value. An explanatory message is output, and execution of the program is terminated.

7 Accuracy

The errors are negligible.

8 Further Comments

The total number of floating-point operations is approximately proportional to nm.

The complex analogue of this routine is F08NWF (CGEBAK/ZGEBAK).

9 Example

See Section 9 of the document for F08NHF (SGEBAL/DGEBAL).