NAG Fortran Library Routine Document G02DKF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G02DKF calculates the estimates of the parameters of a general linear regression model for given constraints from the singular value decomposition results.

2 Specification

```
SUBROUTINE GO2DKF(IP, ICONST, P, C, LDC, B, RSS, IDF, SE, COV, WK,

IFAIL)

INTEGER

IP, ICONST, LDC, IDF, IFAIL

real

P(IP*IP+2*IP), C(LDC,ICONST), B(IP), RSS, SE(IP),

COV((IP*(IP+1)/2)),

WK(2*IP*IP+IP*ICONST+2*ICONST*ICONST+4*ICONST)
```

3 Description

This routine computes the estimates given a set of linear constraints for a general linear regression model which is not of full rank. It is intended for use after a call to G02DAF or G02DDF.

In the case of a model not of full rank the routines use a singular value decomposition (SVD) to find the parameter estimates, $\hat{\beta}_{\text{svd}}$, and their variance-covariance matrix. Details of the SVD are made available in the form of the matrix P^* :

$$P^* = \begin{pmatrix} D^{-1} P_1^T \\ P_0^T \end{pmatrix},$$

as described by G02DAF and G02DDF.

Alternative solutions can be formed by imposing constraints on the parameters. If there are p parameters and the rank of the model is k, then $n_c = p - k$ constraints will have to be imposed to obtain a unique solution.

Let C be a p by n_c matrix of constraints, such that

$$C^{\mathrm{T}}\beta = 0$$

then the new parameter estimates $\hat{\beta}_c$ are given by

$$\hat{\beta}_c = A\hat{\beta}_{\text{svd}}$$

$$= (I - P_0(C^T P_0)^{-1})\hat{\beta}_{\text{svd}},$$

where I is the identity matrix, and the variance-covariance matrix is given by

$$AP_{1}D^{-2}P_{1}^{T}A^{T}$$
,

provided $(C^{T}P_{0})^{-1}$ exists.

[NP3546/20A] G02DKF.1

4 References

Golub G H and van Loan C F (1996) Matrix Computations (3rd Edition) Johns Hopkins University Press, Baltimore

Hammarling S (1985) The singular value decomposition in multivariate statistics SIGNUM Newsl. **20 (3)** 2–25

Searle S R (1971) Linear Models Wiley

5 Parameters

1: IP – INTEGER Input

On entry: the number of terms in the linear model, p.

Constraint: $IP \geq 1$.

2: ICONST – INTEGER

Input

On entry: the number of constraints to be imposed on the parameters, n_c .

Constraint: 0 < ICONST < IP.

3: P(IP*IP+2*IP) - real array

Input

On entry: P as returned by G02DAF and G02DDF.

4: C(LDC,ICONST) – *real* array

Input

On entry: the ICONST constraints stored by column, i.e., the ith constraint is stored in the ith column of C.

5: LDC – INTEGER

Input

On entry: the first dimension of the array C as declared in the (sub)program from which G02DKF is called.

Constraint: LDC \geq IP.

6: B(IP) - real array

Input/Output

On entry: the parameter estimates computed by using the singular value decomposition, $\hat{\beta}_{\text{svd}}$.

On exit: the parameter estimates of the parameters with the constraints imposed, $\hat{\beta}_c$.

7: RSS – real Input

On entry: the residual sum of squares as returned by G02DAF or G02DDF.

Constraint: RSS > 0.0.

8: IDF – INTEGER

Input

On entry: the degrees of freedom associated with the residual sum of squares as returned by G02DAF or G02DDF.

Constraint: IDF > 0.

9: SE(IP) - real array

Output

On entry: the standard error of the parameter estimates in B.

G02DKF.2 [NP3546/20A]

```
10: COV((IP*(IP+1)/2)) - real array
```

Output

On exit: the upper triangular part of the variance-covariance matrix of the IP parameter estimates given in B. They are stored packed by column, i.e., the covariance between the parameter estimate given in B(i) and the parameter estimate given in B(j), $j \ge i$, is stored in $COV(j \times (j-1)/2 + i)$.

11: WK(2*IP*IP+IP*ICONST+2*ICONST*ICONST+4*ICONST) – *real* array

Workspace

Note that a simple upper bound for the size of the workspace is $5 \times IP \times IP$.

12: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1
```

```
\begin{array}{lll} \text{On entry,} & IP < 1, \\ \text{or} & ICONST \leq 0, \\ \text{or} & ICONST \geq IP, \\ \text{or} & LDC < IP, \\ \text{or} & RSS \leq 0.0, \\ \text{or} & IDF \leq 0. \end{array}
```

IFAIL = 2

C does not give a model of full rank.

7 Accuracy

It should be noted that due to rounding errors a parameter that should be zero when the constraints have been imposed may be returned as a value of order *machine precision*.

8 Further Comments

This routine is intended for use in situations in which dummy (0–1) variables have been used such as in the analysis of designed experiments when the user does not wish to change the parameters of the model to give a full rank model. The routine is not intended for situations in which the relationships between the independent variables are only approximate.

9 Example

Data from an experiment with four treatments and three observations per treatment are read in. A model, including the mean term, is fitted by G02DAF and the results printed. The constraint that the sum of treatment effect is zero is then read in and the parameter estimates with this constraint imposed are computed by G02DKF and printed.

[NP3546/20A] G02DKF.3

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO2DKF Example Program Text
   Mark 14 Release. NAG Copyright 1989.
   .. Parameters ..
                     MMAX, NMAX
   INTEGER
  PARAMETER
                     (MMAX=5,NMAX=12)
   INTEGER
                     NIN, NOUT
   PARAMETER
                    (NIN=5,NOUT=6)
   .. Local Scalars ..
  real
                    RSS, TOL
   INTEGER
                    I, ICONST, IDF, IFAIL, IP, IRANK, J, M, N
  LOGICAL
                    SVD
   CHARACTER
                    MEAN, WEIGHT
   .. Local Arrays ..
                    B(MMAX), C(MMAX,MMAX), COV((MMAX*MMAX+MMAX)/2),
                     H(NMAX), P(MMAX*(MMAX+2)), Q(NMAX,MMAX+1),
                     RES(NMAX), SE(MMAX), WK(4*MMAX*MMAX+5*(MMAX-1)),
                     WT(NMAX), X(NMAX, MMAX), Y(NMAX)
  INTEGER
                    ISX(MMAX)
   .. External Subroutines ..
  EXTERNAL
                    GO2DAF, GO2DKF
   .. Executable Statements ..
   WRITE (NOUT,*) 'GO2DKF Example Program Results'
   Skip heading in data file
   READ (NIN,*)
  READ (NIN,*) N, M, WEIGHT, MEAN
  WRITE (NOUT,*)
   IF (N.LE.NMAX .AND. M.LT.MMAX) THEN
      IF (WEIGHT.EQ.'W' .OR. WEIGHT.EQ.'w') THEN
         DO 20 I = 1, N
            READ (NIN,*) (X(I,J),J=1,M), Y(I), WT(I)
         CONTINUE
20
      ELSE
         DO 40 I = 1, N
            READ (NIN,*) (X(I,J),J=1,M), Y(I)
40
         CONTINUE
      END IF
      READ (NIN, \star) (ISX(J), J=1, M), IP
      Set tolerance
      TOL = 0.00001e0
      IFAIL = 0
      Find initial estimates using GO2DAF
      CALL GO2DAF (MEAN, WEIGHT, N, X, NMAX, M, ISX, IP, Y, WT, RSS, IDF, B, SE,
                   COV, RES, H, Q, NMAX, SVD, IRANK, P, TOL, WK, IFAIL)
      WRITE (NOUT,*) 'Estimates from GO2DAF'
      WRITE (NOUT, *)
      WRITE (NOUT, 99999) 'Residual sum of squares = ', RSS
      WRITE (NOUT,99998) 'Degrees of freedom = ', IDF
      WRITE (NOUT, *)
      WRITE (NOUT, *)
        'Variable
                     Parameter estimate
                                            Standard error'
      WRITE (NOUT, *)
      DO 60 J = 1, IP
         WRITE (NOUT, 99997) J, B(J), SE(J)
60
      CONTINUE
      Input constraints and call GO2DKF
      ICONST = IP - IRANK
      DO 80 I = 1, IP
         READ (NIN,*) (C(I,J),J=1,ICONST)
80
      CONTINUE
      IFAIL = 0
      CALL GO2DKF(IP, ICONST, P, C, MMAX, B, RSS, IDF, SE, COV, WK, IFAIL)
```

G02DKF.4 [NP3546/20A]

```
WRITE (NOUT, *)
         WRITE (NOUT,*) 'Estimates from GO2DKF using constraints'
         WRITE (NOUT, *)
         WRITE (NOUT, *)
          'Variable Parameter estimate Standard error'
         WRITE (NOUT, *)
         DO 100 J = 1, IP
            WRITE (NOUT, 99997) J, B(J), SE(J)
 100
         CONTINUE
     END IF
     STOP
99999 FORMAT (1X,A,e13.4)
99998 FORMAT (1X,A,I4)
99997 FORMAT (1X, 16, 2e20.4)
     END
```

9.2 Program Data

```
GO2DKF Example Program Data
12 4 'U' 'M'
1.0 0.0 0.0 0.0 33.63
0.0 0.0 0.0 1.0 39.62
0.0 1.0 0.0 0.0 38.18
0.0 0.0 1.0 0.0 41.46
0.0 0.0 0.0 1.0 38.02
0.0 1.0 0.0 0.0 35.83
0.0 0.0 0.0 1.0 35.99
1.0 0.0 0.0 0.0 36.58
0.0 0.0 1.0 0.0 42.92
1.0 0.0 0.0 0.0 37.80
0.0 0.0 1.0 0.0 40.43
0.0 1.0 0.0 0.0 37.89
1
     1
        1
            1
0.0
1.0
1.0
1.0
1.0
```

9.3 Program Results

```
GO2DKF Example Program Results
Estimates from GO2DAF
Residual sum of squares =
                           0.2223E+02
Degrees of freedom =
Variable
         Parameter estimate Standard error
               0.3056E+02
     1
                                  0.3849E+00
     2
               0.5447E+01
                                  0.8390E+00
     3
               0.6743E+01
                                   0.8390E+00
     4
               0.1105E+02
                                   0.8390E+00
               0.7320E+01
                                   0.8390E+00
Estimates from GO2DKF using constraints
Variable
          Parameter estimate
                               Standard error
               0.3820E+02
                                   0.4812E+00
     1
     2
              -0.2192E+01
                                   0.8334E+00
     3
              -0.8958E+00
                                   0.8334E+00
               0.3408E+01
     4
                                  0.8334E+00
     5
              -0.3192E+00
                                  0.8334E+00
```

[NP3546/20A] G02DKF.5 (last)