Output

NAG Fortran Library Routine Document

G05ECF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G05ECF sets up the reference vector R for a Poisson distribution with mean t.

2 Specification

SUBROUTINE GO5ECF(T, R, NR, IFAIL)
INTEGER NR, IFAIL
real T, R(NR)

3 Description

G05ECF sets up a reference vector for use in G05EYF. Together these routines produce random numbers from the distribution defined by:

$$P(I=i) = \frac{t^i e^{-t}}{i!}$$
 if $i = 0, 1, ...,$

$$P(I = i) = 0$$
 otherwise.

The reference array is found using a recurrence relation if t is less than 50 and by Stirling's formula otherwise.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison-Wesley Kendall M G and Stuart A (1969) *The Advanced Theory of Statistics (Volume 1)* (3rd Edition) Griffin

5 Parameters

1: T - real Input

On entry: the mean, t, of the distribution.

Constraint: $T \ge 0$.

2: R(NR) - real array

On exit: the reference vector.

3: NR – INTEGER Input

On entry: the dimension of the array R as declared in the (sub)program from which G05ECF is called.

Suggested value: approximately $20 + 20 \times \sqrt{T}$ (for optimum efficiency in G05EYF).

Constraint: NR > $(INT[T + 7.15\sqrt{T} + 8.5] - max(0, INT[T - 7.15\sqrt{T}]) + 4)$.

4: IFAIL – INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

[NP3546/20A] G05ECF.1

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
\begin{split} \text{IFAIL} &= 1 \\ &\quad \text{On entry, } T < 0. \\ \\ \text{IFAIL} &= 2 \\ &\quad \text{On entry, NR is too small (see Section 5).} \end{split}
```

7 Accuracy

Not applicable.

8 Further Comments

The time taken by the routine increases with NR.

9 Example

The example program sets up a reference for a Poisson distribution with mean 2.7 and then prints the first five pseudo-random numbers generated by G05EYF, after initialisation by G05CBF.

The generator mechanism used is selected by an initial call to G05ZAF.

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO5ECF Example Program Text
Mark 20 Revised. NAG Copyright 2001.
.. Parameters ..
INTEGER
                 NR
                  (T=2.7e0, NR=30)
PARAMETER
INTEGER
                 NOUT
PARAMETER
                  (NOUT=6)
.. Local Scalars ..
                 I, IFAIL, IX
INTEGER
.. Local Arrays ..
real
                 R(NR)
.. External Functions ..
INTEGER
                 G05EYF
EXTERNAL
                 G05EYF
.. External Subroutines ..
EXTERNAL
                 GO5CBF, GO5ECF, GO5ZAF
.. Executable Statements ..
CALL GO5ZAF('O')
WRITE (NOUT,*) 'GO5ECF Example Program Results'
WRITE (NOUT, *)
CALL GO5CBF(0)
```

G05ECF.2 [NP3546/20A]

9.2 Program Data

None.

9.3 Program Results

GOSECF Example Program Results

4
1
2
1
5

[NP3546/20A] G05ECF.3 (last)