

NAG Fortran Library Routine Document

G05MBF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

G05MBF generates a vector of pseudo-random integers from the discrete geometric distribution with probability p of success at a trial.

2 Specification

```
SUBROUTINE G05MBF(MODE, P, N, X, IGEN, ISEED, R, NR, IFAIL)
INTEGER          MODE, N, X(N), IGEN, ISEED(4), NR, IFAIL
real           P, R(NR)
```

3 Description

G05MBF generates n integers x_i from a discrete geometric distribution, where the probability of $x_i = I$ (a first success after I trials) is

$$P(x_i = I) = p \times [(1 - p)^{(I-1)}], \quad I = 1, 2, \dots$$

The variates can be generated with or without using a search table and index. If a search table is used then it is stored with the index in a reference vector and subsequent calls to G05MBF with the same parameter value can then use this reference vector to generate further variates. If the search table is not used (as recommended for small values of p) then a direct transformation of uniform variates is used.

One of the initialisation routines G05KBF (for a repeatable sequence if computed sequentially) or G05KCF (for a non-repeatable sequence) must be called prior to the first call to G05MBF.

4 References

Knuth D E (1981) *The Art of Computer Programming (Volume 2)* (2nd Edition) Addison-Wesley

5 Parameters

1: MODE – INTEGER *Input*

On entry: a code for selecting the operation to be performed by the routine:

MODE = 0

Set up reference vector only.

MODE = 1

Generate variates using reference vector set up in a prior call to G05MBF.

MODE = 2

Set up reference vector and generate variates.

MODE = 3

Generate variates without using the reference vector;

Constraint: MODE = 0, 1, 2 or 3.

- 2: P – *real* *Input*
On entry: the parameter p of the geometric distribution representing the probability of success at a single trial.
Constraint: *machine precision* $\leq P \leq 1.0$.
- 3: N – INTEGER *Input*
On entry: the number, n , of pseudo-random numbers to be generated.
Constraint: $N \geq 1$.
- 4: X(N) – INTEGER array *Output*
On exit: the n pseudo-random numbers from the specified geometric distribution.
- 5: IGEN – INTEGER *Input*
On entry: must contain the identification number for the generator to be used to return a pseudo-random number and should remain unchanged following initialisation by a prior call to one of the routines G05KBF or G05KCF.
- 6: ISEED(4) – INTEGER array *Input/Output*
On entry: contains values which define the current state of the selected generator.
On exit: contains updated values defining the new state of the selected generator.
- 7: R(NR) – *real* array *Input/Output*
On exit: the reference vector.
- 8: NR – INTEGER *Input*
On entry: the dimension of the array R as declared in the (sub)program from which G05MBF is called.
Suggested value: approximately $6 + 42/P$ (for optimum efficiency in G05EYF).
Constraints:
 if MODE = 0 or 2, then $NR \geq 30/P + 6$;
 if MODE = 1, then NR should remain unchanged from the previous call to G05MBF;
 if MODE = 3, then R is not referenced.
- 9: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $N < 1$.

IFAIL = 2

On entry, $NR < 30/P + 6$ and $MODE = 0$ or 2 .

IFAIL = 3

On entry, $P < \textit{machine precision}$,
or $P > 1.0$.

IFAIL = 4

On entry, $MODE < 0$,
or $MODE > 3$.

IFAIL = 5

$MODE = 0$ or 2 and P is so small that NR would have to be larger than the largest representable integer. Use $MODE = 3$ in this case.

IFAIL = 6

P is not the same as when R was set up in a previous call with $MODE = 0$ or 2 .

7 Accuracy

Not applicable.

8 Further Comments

The time taken to set up the reference vector, if used, increases with NR . However, if the reference vector is used, the time taken to generate numbers decreases as the space allotted to the index part of R increases. There is a point, depending on the distribution, where this improvement becomes very small and the recommended values for NR in other routines are designed to approximate this point.

If P is very small then the storage requirements for the reference vector and the time taken to set up the reference vector becomes prohibitive. In this case it is recommended that the reference vector is not used. This is achieved by selecting $MODE = 3$.

9 Example

The example program prints five pseudo-random integers from a geometric distribution with parameter $p = 0.001$, generated by a single call to G05MBF, after initialisation by G05KBF.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      G05MBF Example Program Text
*      Mark 20 Release. NAG Copyright 2001.
*      .. Parameters ..
      INTEGER          NOUT, N, NR
      PARAMETER        (NOUT=6,N=10,NR=40000)
*      .. Local Scalars ..
      real              P
      INTEGER          IFAIL, IGEN
*      .. Local Arrays ..
      real              R(NR)
      INTEGER          ISEED(4), X(N)
*      .. External Subroutines ..
```

```
EXTERNAL          G05KBF, G05MBF
*    .. Executable Statements ..
WRITE (NOUT,*) 'G05MBF Example Program Results'
WRITE (NOUT,*)
*    Set the distribution parameter P
P = 0.001e0
*    Initialise the seed to a repeatable sequence
ISEED(1) = 1762543
ISEED(2) = 9324783
ISEED(3) = 423441
ISEED(4) = 742355
*    IGEN identifies the stream.
IGEN = 1
CALL G05KBF(IGEN,ISEED)
*    Choose MODE = 3 because P is close to 0
IFAIL = 0
CALL G05MBF(3,P,N,X,IGEN,ISEED,R,NR,IFAIL)
*
WRITE (NOUT,99999) X
STOP
*
99999 FORMAT (1X,I12)
END
```

9.2 Program Data

None.

9.3 Program Results

G05MBF Example Program Results

```
3699
631
29
1228
481
341
1394
915
332
487
```
