NAG Fortran Library Routine Document S10ABF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

S10ABF returns the value of the hyperbolic sine, $\sinh x$, via the routine name.

2 Specification

3 Description

The routine calculates an approximate value for the hyperbolic sine of its argument, $\sinh x$.

For $|x| \le 1$ it uses the Chebyshev expansion

$$\sinh x = x \times y(t) = x \sum_{r=0}^{\prime} a_r T_r(t)$$

where $t = 2x^2 - 1$.

For
$$1 < |x| \le E_1$$
, $\sinh x = \frac{1}{2}(e^x - e^{-x})$

where E_1 is a machine-dependent constant, details of which are given in the Users' Note for your implementation.

For $|x| > E_1$, the routine fails owing to the danger of setting overflow in calculating e^x . The result returned for such calls is $\sinh(\operatorname{sign} x E_1)$, i.e., it returns the result for the nearest valid argument.

4 References

Abramowitz M and Stegun I A (1972) Handbook of Mathematical Functions (3rd Edition) Dover Publications

5 Parameters

1: X – **real** Input

On entry: the argument x of the function.

2: IFAIL – INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

[NP3546/20A] S10ABF.1

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

The routine has been called with an argument too large in absolute magnitude. There is a danger of setting overflow. The result is the value of sinh at the closest argument for which a valid call could be made. (See Section 3 and the Users' Note for your implementation.)

7 Accuracy

If δ and ϵ are the relative errors in the argument and result, respectively, then in principle

$$|\epsilon| \simeq |x \coth x \times \delta|$$
.

That is the relative error in the argument, x, is amplified by a factor, approximately $x \coth x$. The equality should hold if δ is greater than the **machine precision** (δ is a result of data errors etc.) but, if δ is simply a result of round-off in the machine representation of x, then it is possible that an extra figure may be lost in internal calculation round-off.

The behaviour of the error amplification factor can be seen in the following graph:




Figure 1

It should be noted that for $|x| \ge 2$

$$\epsilon \sim x\delta = \Delta$$

where Δ is the absolute error in the argument.

8 Further Comments

None.

S10ABF.2 [NP3546/20A]

9 Example

The example program reads values of the argument x from a file, evaluates the function at each value of x and prints the results.

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
S10ABF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
      INTEGER
                       NIN, NOUT
                       (NIN=5, NOUT=6)
     PARAMETER
      .. Local Scalars ..
     INTEGER
                       Х, Ү
                       IFAIL
      .. External Functions ..
     real
                     S10ABF
     EXTERNAL
                       S10ABF
      .. Executable Statements ..
      WRITE (NOUT,*) 'S10ABF Example Program Results'
      Skip heading in data file
      READ (NIN, *)
     WRITE (NOUT, *)
     WRITE (NOUT, *) '
                                       Y
                                                 IFAIL'
     WRITE (NOUT, *)
   20 READ (NIN, \star, END=40) X
      IFAIL = 1
      Y = S1OABF(X,IFAIL)
      WRITE (NOUT, 99999) X, Y, IFAIL
      GO TO 20
   40 STOP
99999 FORMAT (1X,1P,2e12.3,I7)
      END
```

9.2 Program Data

```
S10ABF Example Program Data
-10.0
-0.5
0.0
0.5
25.0
```

9.3 Program Results

S10ABF Example Program Results

X	Y	IFAIL
-1.000E+01 -5.000E-01 0.000E+00 5.000E-01 2.500E+01	-1.101E+04 -5.211E-01 0.000E+00 5.211E-01 3.600E+10	0 0 0 0

[NP3546/20A] S10ABF.3 (last)