

NAG Fortran Library Routine Document

S17AGF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

S17AGF returns a value for the Airy function, $\text{Ai}(x)$, via the routine name.

2 Specification

```
real FUNCTION S17AGF(X, IFAIL)
  INTEGER          IFAIL
real              X
```

3 Description

This routine evaluates an approximation to the Airy function, $\text{Ai}(x)$. It is based on a number of Chebyshev expansions:

For $x < -5$,

$$\text{Ai}(x) = \frac{a(t) \sin z - b(t) \cos z}{(-x)^{1/4}}$$

where $z = \frac{\pi}{4} + \frac{2}{3}\sqrt{-x^3}$, and $a(t)$ and $b(t)$ are expansions in the variable $t = -2\left(\frac{5}{x}\right)^3 - 1$.

For $-5 \leq x \leq 0$,

$$\text{Ai}(x) = f(t) - xg(t),$$

where f and g are expansions in $t = -2\left(\frac{x}{5}\right)^3 - 1$.

For $0 < x < 4.5$,

$$\text{Ai}(x) = e^{-3x/2}y(t),$$

where y is an expansion in $t = 4x/9 - 1$.

For $4.5 \leq x < 9$,

$$\text{Ai}(x) = e^{-5x/2}u(t),$$

where u is an expansion in $t = 4x/9 - 3$.

For $x \geq 9$,

$$\text{Ai}(x) = \frac{e^{-z}v(t)}{x^{1/4}},$$

where $z = \frac{2}{3}\sqrt{x^3}$ and v is an expansion in $t = 2\left(\frac{18}{z}\right) - 1$.

For $|x| < \textit{machine precision}$, the result is set directly to $\text{Ai}(0)$. This both saves time and guards against underflow in intermediate calculations.

For large negative arguments, it becomes impossible to calculate the phase of the oscillatory function with any precision and so the routine must fail. This occurs if $x < -\left(\frac{3}{2\epsilon}\right)^{2/3}$, where ϵ is the **machine precision**.

For large positive arguments, where Ai decays in an essentially exponential manner, there is a danger of underflow so the routine must fail.

4 References

Abramowitz M and Stegun I A (1972) *Handbook of Mathematical Functions* (3rd Edition) Dover Publications

5 Parameters

1: X – *real* *Input*

On entry: the argument x of the function.

2: IFAIL – INTEGER *Input/Output*

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

X is too large and positive. On soft failure, the routine returns zero.

IFAIL = 2

X is too large and negative. On soft failure, the routine returns zero.

7 Accuracy

For negative arguments the function is oscillatory and hence absolute error is the appropriate measure. In the positive region the function is essentially exponential-like and here relative error is appropriate. The absolute error, E , and the relative error, ϵ , are related in principle to the relative error in the argument, δ , by

$$E \simeq |x \text{Ai}'(x)|\delta, \quad \epsilon \simeq \left| \frac{x \text{Ai}'(x)}{\text{Ai}(x)} \right| \delta.$$

In practice, approximate equality is the best that can be expected. When δ , ϵ or E is of the order of the **machine precision**, the errors in the result will be somewhat larger.

For small x , errors are strongly damped by the function and hence will be bounded by the **machine precision**.

For moderate negative x , the error behaviour is oscillatory but the amplitude of the error grows like

$$\text{amplitude} \left(\frac{E}{\delta} \right) \sim \frac{|x|^{5/4}}{\sqrt{\pi}}.$$

However the phase error will be growing roughly like $\frac{2}{3}\sqrt{|x|^3}$ and hence all accuracy will be lost for large negative arguments due to the impossibility of calculating sin and cos to any accuracy if $\frac{2}{3}\sqrt{|x|^3} > \frac{1}{\delta}$.

For large positive arguments, the relative error amplification is considerable:

$$\frac{\epsilon}{\delta} \sim \sqrt{x^3}.$$

This means a loss of roughly two decimal places accuracy for arguments in the region of 20. However very large arguments are not possible due to the danger of setting underflow and so the errors are limited in practice.

8 Further Comments

None.

9 Example

The example program reads values of the argument x from a file, evaluates the function at each value of x and prints the results.

9.1 Program Text

Note: the listing of the example program presented below uses ***bold italicised*** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      S17AGF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER        (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real              X, Y
      INTEGER          IFAIL
*      .. External Functions ..
      real              S17AGF
      EXTERNAL          S17AGF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'S17AGF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      WRITE (NOUT,*)
      WRITE (NOUT,*) '          X          Y          IFAIL'
      WRITE (NOUT,*)
20    READ (NIN,*,END=40) X
      IFAIL = 1
*
      Y = S17AGF(X,IFAIL)
*
      WRITE (NOUT,99999) X, Y, IFAIL
      GO TO 20
40    STOP
*
99999 FORMAT (1X,1P,2e12.3,I7)
      END
```

9.2 Program Data

S17AGF Example Program Data

```
-10.0  
-1.0  
0.0  
1.0  
5.0  
10.0  
20.0
```

9.3 Program Results

S17AGF Example Program Results

X	Y	IFAIL
-1.000E+01	4.024E-02	0
-1.000E+00	5.356E-01	0
0.000E+00	3.550E-01	0
1.000E+00	1.353E-01	0
5.000E+00	1.083E-04	0
1.000E+01	1.105E-10	0
2.000E+01	1.692E-27	0
