

NAG Fortran Library Routine Document

F06HTF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F06FRF applies a complex elementary reflection (Householder matrix) P , as generated by F06HRE, to a given complex vector:

$$\begin{pmatrix} \delta \\ y \end{pmatrix} \leftarrow P \begin{pmatrix} \delta \\ y \end{pmatrix}$$

where y is an n element complex vector and δ is a complex scalar.

To apply the conjugate transpose matrix P^H , call F06HTF with $\bar{\theta}$ in place of θ .

2 Specification

```
SUBROUTINE F06HTF (N, DELTA, Y, INCY, THETA, Z, INCZ)
  INTEGER          N, INCY, INCZ
  complex*16      DELTA, Y(*), THETA, Z(*)
```

3 Description

None.

4 References

None.

5 Parameters

- | | | |
|----|--|---------------------|
| 1: | N – INTEGER | <i>Input</i> |
| | <i>On entry:</i> n , the number of elements in y and z . | |
| 2: | DELTA – complex*16 | <i>Input/Output</i> |
| | <i>On entry:</i> the original scalar δ . | |
| | <i>On exit:</i> the transformed scalar δ . | |
| 3: | Y(*) – complex*16 array | <i>Input/Output</i> |
| | <i>On entry:</i> the original vector y . | |
| | <i>On exit:</i> the transformed vector y . | |
| 4: | INCY – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the increment in the subscripts of Y between successive elements of y . | |
| 5: | THETA – complex*16 | <i>Input</i> |
| | <i>On entry:</i> the value θ , as returned by F06HRE. If $\theta = 0$, P is assumed to be the unit matrix and the transformation is skipped. | |
| | <i>Constraint:</i> if THETA ≤ 0 , $n = 0$. | |

- 6: $Z(*)$ – **complex*16** array *Input*
On entry: the vector z , as returned by F06HRF.
- 7: INCZ – INTEGER *Input*
On entry: the increment in the subscripts of Z between successive elements of z .

6 Error Indicators and Warnings

None.
