NAG Fortran Library Routine Document F06PJF (DTRSV)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F06PJF (DTRSV) performs one of the matrix-vector operations

$$x \leftarrow A^{-1}x$$
 or $x \leftarrow A^{-T}x$,

where A is an n by n real triangular matrix, and x is an n element real vector. A^{-T} denotes $(A^T)^{-1}$ or equivalently $(A^{-1})^T$.

No test for singularity or near-singularity of A is included in this routine. Such tests must be performed before calling this routine.

2 Specification

SUBROUTINE FO6PJF (UPLO, TRANS, DIAG, N, A, LDA, X, INCX)

INTEGER N, LDA, INCX

double precision A(LDA,*), X(*)

CHARACTER*1 UPLO, TRANS, DIAG

The routine may be called by its BLAS name dtrsv.

3 Description

None.

4 References

None.

5 Parameters

1: UPLO – CHARACTER*1

Input

On entry: specifies whether A is upper or lower triangular as follows:

if UPLO = 'U', A is upper triangular; if UPLO = 'L', A is lower triangular.

Constraint: UPLO = 'U' or 'L'.

2: TRANS – CHARACTER*1

Input

On entry: specifies the operation to be performed as follows:

if TRANS = 'N',
$$x \leftarrow A^{-1}x$$
;
if TRANS = 'T' or 'C', $x \leftarrow A^{-T}x$.

Constraint: TRANS = 'N', 'T' or 'C'.

3: DIAG - CHARACTER*1

Input

On entry: specifies whether A has non-unit or unit diagonal elements, as follows:

if DIAG = 'N', the diagonal elements are stored explicitly;

if DIAG = 'U', the diagonal elements are assumed to be 1, and are not referenced.

Constraint: DIAG = 'N' or 'U'.

4: N – INTEGER

Input

On entry: n, the order of the matrix A.

Constraint: $N \geq 0$.

5: A(LDA,*) – *double precision* array

Input

Note: the second dimension of the array A must be at least max(1, N).

On entry: the n by n triangular matrix A. If UPLO = 'U', A is upper triangular and the elements of the array below the diagonal are not referenced; if UPLO = 'L', A is lower triangular and the elements of the array above the diagonal are not referenced. If DIAG = 'U', the diagonal elements of A are not referenced, but are assumed to be 1.

6: LDA – INTEGER

Input

On entry: the first dimension of the array A as declared in the (sub)program from which F06PJF (DTRSV) is called.

Constraint: LDA $\geq \max(1, N)$.

7: X(*) – *double precision* array

Input/Output

On entry: the vector x.

On exit: the updated vector x.

8: INCX – INTEGER

Input

On entry: the increment in the subscripts of X between successive elements of x.

Constraint: INCX \neq 0.

6 Error Indicators and Warnings

None.