# NAG Fortran Library Routine Document G05HLF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

G05HLF generates a given number of terms of a type II AGARCH(p,q) process (see Engle and Ng (1993)).

# 2 Specification

```
SUBROUTINE GO5HLF(DIST, NUM, IP, IQ, THETA, GAMMA, DF, HT, ET, FCALL,

RVEC, IGEN, ISEED, RWSAV, IFAIL)

INTEGER

NUM, IP, IQ, IGEN, ISEED(4), IFAIL

real

THETA(IQ+IP+1), GAMMA, DF, HT(NUM), ET(NUM), RVEC(40),

RWSAV(9)

LOGICAL
CHARACTER*1

DIST
```

# 3 Description

A type II AGARCH(p,q) process can be represented by:

$$h_t = \alpha_0 + \sum_{i=1}^q \alpha_i (|\epsilon_{t-i}| + \gamma \epsilon_{t-i})^2 + \sum_{i=1}^p \beta_i h_{t-i}, \quad t = 1, \dots, T.$$

where  $\epsilon_t|\psi_{t-1}=N(0,h_t)$  or  $\epsilon_t|\psi_{t-1}=S_t(df,h_t)$ . Here  $S_t$  is a standardised Student's t-distribution with df degrees of freedom and variance  $h_t$ , T is the number of observations in the sequence,  $\epsilon_t$  is the observed value of the GARCH(p,q) process at time t,  $h_t$  is the conditional variance at time t, and  $\psi_t$  the set of all information up to time t. Symmetric GARCH sequences are generated when  $\gamma$  is zero, otherwise asymmetric GARCH sequences are generated with  $\gamma$  specifying the amount by which positive (or negative) shocks are to be enhanced.

One of the initialisation routines G05KBF (for a repeatable sequence if computed sequentially) or G05KCF (for a non-repeatable sequence) must be called prior to the first call to G05HLF.

## 4 References

Engle R (1982) Autoregressive conditional heteroskedasticity with estimates of the variance of United Kingdom inflation *Econometrica* **50** 987–1008

Bollerslev T (1986) Generalised autoregressive conditional heteroskedasticity *Journal of Econometrics* **31** 307–327

Engle R and Ng V (1993) Measuring and Testing the Impact of News on Volatility *Journal of Finance* **48** 1749–1777

Hamilton J (1994) Time Series Analysis Princeton University Press

## 5 Parameters

1: DIST – CHARACTER\*1

Input

On entry: the type of distribution to use for  $\epsilon_t$ .

DIST = 'N'

Then a Normal distribution is used.

[NP3546/20A] G05HLF.1

DIST = T'

Then a Student's t-distribution is used.

Constraint: DIST = 'N' or 'T'.

#### 2: NUM – INTEGER

Input

On entry: the number of terms in the sequence, T.

Constraint: NUM > 0.

3: IP – INTEGER

Input

On entry: the number of coefficients,  $\beta_i$ , for i = 1, ..., p.

Constraints:

$$\begin{aligned} &IQ + IP + 1 \leq 20, \\ &IP \geq 0. \end{aligned}$$

4: IQ – INTEGER

Input

On entry: the number of coefficients,  $\alpha_i$ , for  $i = 1, \dots, q$ .

Constraints:

$$\begin{aligned} &IQ+IP+1\leq 20,\\ &IQ\geq 1. \end{aligned}$$

5: THETA(IQ+IP+1) – *real* array

Input

On entry: the first element contains the coefficient  $\alpha_o$ , the next IQ elements contain the coefficients  $\alpha_i$ , for  $i=1,\ldots,q$ . The remaining IP elements are the coefficients  $\beta_i$ , for  $j=1,\ldots,p$ .

6: GAMMA – real

Input

On entry: the asymmetry parameter  $\gamma$  for the GARCH(p,q) sequence.

7: **DF** – *real* 

Input

On entry: the number of degrees of freedom for the Student's t-distribution. It is not referenced if DIST = 'N'.

Constraint: DF > 2.

8: HT(NUM) - real array

Output

On exit: the conditional variances  $h_t$ , for t = 1, ..., T for the GARCH(p, q) sequence.

9: ET(NUM) – *real* array

Output

On exit: the observations  $\epsilon_t$ , for  $t=1,\ldots,T$  for the GARCH(p,q) sequence.

10: FCALL – LOGICAL

Input

On entry: if FCALL = .TRUE., a new sequence is to be generated, otherwise a given sequence is to be continued using the information in RVEC.

11: RVEC(40) - real array

Input/Output

On entry: the array contains information required to continue a sequence if FCALL = .FALSE..

On exit: contains information that can be used in a subsequent call of G05HLF, with FCALL = .FALSE..

[NP3546/20A]

#### 12: IGEN – INTEGER

Input

On entry: must contain the identification number for the generator to be used to return a pseudorandom number and should remain unchanged following initialisation by a prior call to one of the routines G05KBF or G05KCF.

#### 13: ISEED(4) – INTEGER array

Input/Output

On entry: contains values which define the current state of the selected generator.

On exit: contains updated values defining the new state of the selected generator.

14: RWSAV(9) - real array

Workspace

#### 15: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL  $\neq 0$  on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
\begin{split} IFAIL &= 1 \\ On \ entry, \ IP < 0, \\ or \qquad IQ < 1, \\ or \qquad DF \leq 2, \\ or \qquad NUM \leq 0, \end{split}
```

or DIST  $\neq$  'N', and DIST  $\neq$  'T', or IQ + IP + 1 > 20.

# 7 Accuracy

Not applicable.

### **8** Further Comments

None.

# 9 Example

See Section 9 of the document for G13FCF.

[NP3546/20A] G05HLF.3 (last)