# NAG Fortran Library Routine Document G13DMF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

## 1 Purpose

G13DMF calculates the sample cross-correlation (or cross-covariance) matrices of a multivariate time series.

## 2 Specification

SUBROUTINE G13DMF(MATRIX, K, N, M, W, IK, WMEAN, RO, R, IFAIL)

INTEGER

K, N, M, IK, IFAIL

real

W(IK,N), WMEAN(K), RO(IK,K), R(IK,IK,M)

CHARACTER\*1

MATRIX

## 3 Description

Let  $W_t = (w_{1t}, w_{2t}, \dots, w_{kt})^T$ , for  $t = 1, 2, \dots, n$ , denote n observations of a vector of k time series. The sample cross-covariance matrix at lag l is defined to be the k by k matrix  $\hat{C}(l)$ , whose (i, j)th element is given by

$$\hat{C}_{ij}(l) = \frac{1}{n} \sum_{t=l+1}^{n} (w_{i(t-l)} - \bar{w}_i)(w_{jt} - \bar{w}_j), \quad l = 0, 1, 2, \dots, m; \ i = 1, 2, \dots, k; \ j = 1, 2, \dots, k,$$

where  $\bar{w}_i$  and  $\bar{w}_j$  denote the sample means for the *i*th and *j*th series respectively. The sample cross-correlation matrix at lag *l* is defined to be the *k* by *k* matrix  $\hat{R}(l)$ , whose (i, j)th element is given by

$$\hat{R}_{ij}(l) = \frac{\hat{C}_{ij}(l)}{\sqrt{\hat{C}_{ii}(0)\hat{C}_{jj}(0)}}, \quad l = 0, 1, 2, \dots, m; \ i = 1, 2, \dots, k; \ j = 1, 2, \dots, k.$$

The number of lags, m, is usually taken to be at most n/4.

If  $W_t$  follows a vector moving average model of order q, then it can be shown that the theoretical cross-correlation matrices (R(l)) are zero beyond lag q. In order to help spot a possible cut-off point, the elements of  $\hat{R}(l)$  are usually compared to their approximate standard error of  $1/\sqrt{n}$ . For further details see, for example, Wei (1990).

The routine uses a single pass through the data to compute the means and the cross-covariance matrix at lag zero. The cross-covariance matrices at further lags are then computed on a second pass through the data.

#### 4 References

Wei W W S (1990) Time Series Analysis: Univariate and Multivariate Methods Addison-Wesley

West D H D (1979) Updating mean and variance estimates: An improved method *Comm. ACM* 22 532–555

[NP3546/20A] G13DMF.1

### 5 Parameters

### 1: MATRIX – CHARACTER\*1

Input

On entry: indicates whether the cross-covariance or cross-correlation matrices are to be computed.

If MATRIX = 'V', then the cross-covariance matrices are computed;

if MATRIX = 'R', then the cross-correlation matrices are computed.

Constraint: MATRIX = 'V' or 'R'.

#### 2: K – INTEGER

Input

On entry: the dimension, k, of the multivariate time series.

Constraint:  $K \geq 1$ .

3: N – INTEGER

Input

On entry: the number of observations in the series, n.

Constraint:  $N \geq 2$ .

4: M - INTEGER

Input

On entry: the number, m, of cross-correlation (or cross-covariance) matrices to be computed. If in doubt set M = 10. However it should be noted that M is usually taken to be at most N/4.

Constraint:  $1 \le M < N$ .

5: W(IK,N) - real array

Input

On entry: W(i,t) must contain the observation  $w_{it}$ , for  $i=1,2,\ldots,k;\ t=1,2,\ldots,n$ .

6: IK – INTEGER

Input

On entry: the first dimension of the arrays W and R0 and the first and second dimensions of the array R as declared in the (sub)program from which G13DMF is called.

Constraint:  $IK \geq K$ .

7: WMEAN(K) - real array

Output

On exit: the means,  $\bar{w}_i$ , for i = 1, 2, ..., k.

8: R0(IK,K) - real array

Output

On exit: if  $i \neq j$ , then R0(i,j) contains an estimate of the (i,j)th element of the cross-correlation (or cross-covariance) matrix at lag zero,  $\hat{R}_{ij}(0)$ ; if i=j, then if MATRIX = 'V', R0(i,i) contains the variance of the ith series,  $\hat{C}_{ii}(0)$ , and if MATRIX = 'R', R0(i,i) contains the standard deviation of the ith series,  $\sqrt{\hat{C}_{ii}(0)}$ .

If IFAIL = 2 and MATRIX = 'R', then on exit all the elements in R0 whose computation involves the zero variance are set to zero.

#### 9: R(IK,IK,M) - real array

Output

On exit: R(i, j, l) contains an estimate of the (i, j)th element of the cross-correlation (or cross-covariance) at lag l,  $\hat{R}_{ij}(l)$ , for l = 1, 2, ..., m; i = 1, 2, ..., k; j = 1, 2, ..., k.

If IFAIL = 2 and MATRIX = 'R', then on exit all the elements in R whose computation involves the zero variance are set to zero.

G13DMF.2 [NP3546/20A]

#### 10: IFAIL - INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

## 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
IFAIL = 1
```

```
On entry, MATRIX \neq 'V' or 'R', or K < 1, or N < 2, or M < 1, or M \ge N, or IK < K.
```

#### IFAIL = 2

On entry, at least one of the k series is such that all its elements are practically equal giving zero (or near zero) variance. In this case if MATRIX = 'R' all the correlations in R0 and R involving this variance are set to zero.

## 7 Accuracy

For a discussion of the accuracy of the one-pass algorithm used to compute the sample cross-covariances at lag zero see West (1979). For the other lags a two-pass algorithm is used to compute the cross-covariances; the accuracy of this algorithm is also discussed in West (1979). The accuracy of the cross-correlations will depend on the accuracy of the computed cross-covariances.

## **8** Further Comments

The time taken is roughly proportional to  $mnk^2$ .

## 9 Example

This program computes the sample cross-correlation matrices of two time series of length 48, up to lag 10. It also prints the cross-correlation matrices together with plots of symbols indicating which elements of the correlation matrices are significant. Three \* represent significance at the 0.5% level, two \* represent significance at the 1% level and a single \* represents significance at the 5% level. The \* are plotted above or below the line depending on whether the elements are significant in the positive or negative direction.

[NP3546/20A] G13DMF.3

### 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
G13DMF Example Program Text
  Mark 15 Release. NAG Copyright 1991.
   .. Parameters ..
                    NIN, NOUT
   INTEGER
  PARAMETER
                    (NIN=5,NOUT=6)
   INTEGER
                   IK, NMAX, MMAX
                   (IK=3,NMAX=100,MMAX=20)
  PARAMETER
   .. Local Scalars ..
  INTEGER
                   I, IFAIL, J, K, M, N
   .. Local Arrays ..
  real
                    R(IK, IK, MMAX), RO(IK, IK), W(IK, NMAX), WMEAN(IK)
   .. External Subroutines .. EXTERNAL CPRINT, G13DMF
  EXTERNAL
   .. Executable Statements ..
  WRITE (NOUT,*) 'G13DMF Example Program Results'
   Skip heading in data file
   READ (NIN, *)
  READ (NIN,*) K, N, M
  IF (K.GT.O .AND. K.LE.IK .AND. N.GE.1 .AND. N.LE.NMAX .AND. M.GE.
      1 .AND. M.LE.MMAX) THEN
      DO 20 I = 1, K
        READ (NIN,*) (W(I,J),J=1,N)
20
      CONTINUE
      IFAIL = 0
      CALL G13DMF('R',K,N,M,W,IK,WMEAN,RO,R,IFAIL)
      CALL CPRINT(K,N,IK,M,WMEAN,RO,R,NOUT)
  END IF
   STOP
   END
   SUBROUTINE CPRINT(K,N,IK,M,WMEAN,RO,R,NOUT)
   .. Scalar Arguments ..
   INTEGER
                    IK, K, M, N, NOUT
   .. Array Arguments ..
  real
                     R(IK, IK, M), RO(IK, K), WMEAN(K)
   .. Local Scalars ..
  real
                     C1, C2, C3, C5, C6, C7, CONST, SUM
   INTEGER
                    I, I2, IFAIL2, J, L, LL
   .. Local Arrays ..
                REC(7)
                     CLABS(1), RLABS(1)
   CHARACTER*1
   CHARACTER*80
   .. External Subroutines ..
  EXTERNAL
                    XO4CBF
   .. Intrinsic Functions ..
   INTRINSIC
                     real, SQRT
   .. Executable Statements ..
  Print the correlation matrices and indicator symbols.
   CONST = 1.0e0/SQRT(real(N))
   WRITE (NOUT, *)
                 ' THE MEANS'
   WRITE (NOUT, *)
   WRITE (NOUT,*) ' -----
   WRITE (NOUT, 99999) (WMEAN(I), I=1, K)
  WRITE (NOUT, *)
  WRITE (NOUT, *) ' CROSS-CORRELATION MATRICES'
  WRITE (NOUT,*) ' -----
   DO 20 L = 1, M
      WRITE (NOUT, 99998) ' Lag = ', L
      IFAIL2 = 0
      CALL X04CBF('G','N',K,K,R(1,1,L),IK,'F9.3',' ','N',RLABS,'N',
                  CLABS, 80, 5, IFAIL2)
```

G13DMF.4 [NP3546/20A]

```
20 CONTINUE
     Print indicator symbols to indicate significant elements.
*
     WRITE (NOUT,99997) ' Standard error = 1 / SQRT(N) = ', CONST
     WRITE (NOUT, *)
     WRITE (NOUT, *) ' TABLES OF INDICATOR SYMBOLS'
     WRITE (NOUT,*) ' -----'
     WRITE (NOUT, 99998) ' For Lags 1 to ', M
     Set up annotation for the plots.
     WRITE (REC(1),99996) '
                                         0.005
     WRITE (REC(2),99996) '
                                         0.01
     WRITE (REC(3),99996) '
                                         0.05
                                                      : '
     WRITE (REC(4)(1:23),99996) ' Sig. Level
     WRITE (REC(4)(24:),99996) '- - - - - -
                                                     Lags'
     WRITE (REC(5),99996) '
                                        0.05 :'
     WRITE (REC(6),99996) '
                                         0.01
     WRITE (REC(7),99996) '
                                         0.005 :'
     Set up the critical values
     C1 = 3.29e0 * CONST
     C2 = 2.58e0 * CONST
     C3 = 1.96e0 * CONST
     C5 = -C3
     C6 = -C2
     C7 = -C1
     DO 120 I = 1, K
        DO 100 J = 1. K
           WRITE (NOUT, *)
           IF (I.EQ.J) THEN
               WRITE (NOUT, 99995) ' Auto-correlation function for',
                 series ', I
              WRITE (NOUT, 99994) ' Cross-correlation function for',
                ' series ', I, ' and series', J
     +
           END IF
           DO 60 L = 1, M
              LL = 23 + 2*L
              SUM = R(I,J,L)
              Clear the last plot with blanks
              DO 40 I2 = 1, 7
                 IF (I2.NE.4) REC(I2) (LL:LL) = ' '
  40
               CONTINUE
              Check for significance
               IF (SUM.GT.C1) REC(1) (LL:LL) = '*'
              IF (SUM.GT.C2) REC(2) (LL:LL) = '*'
               IF (SUM.GT.C3) REC(3) (LL:LL) = '*'
               IF (SUM.LT.C5) REC(5) (LL:LL) = '*'
               IF (SUM.LT.C6) REC(6) (LL:LL) = '*'
               IF (SUM.LT.C7) REC(7) (LL:LL) = '*'
  60
           CONTINUE
           Print
           DO 80 I2 = 1, 7
              WRITE (NOUT, 99996) REC(I2)
  80
           CONTINUE
  100
        CONTINUE
 120 CONTINUE
     RETURN
99999 FORMAT (/1X,2(2X,F9.3))
99998 FORMAT (/1X,A,I2)
```

[NP3546/20A] G13DMF.5

```
99997 FORMAT (/1X,A,F5.3,A)
99996 FORMAT (1X,A)
99995 FORMAT (//1X,A,A,I2,/)
99994 FORMAT (//1X,A,A,I2,A,I2,/)
      END
```

#### Program Data 9.2

```
G13DMF Example Program Data
2 48 10 : K, no. of series, N, no. of obs in each series, M, no. of lags -1.490 -1.620 5.200 6.230 6.210 5.860 4.090 3.180 2.620 1.490 1.170 0.850 -0.350 0.240 2.440 2.580 2.040 0.400 2.260 3.340 5.090 5.000 4.780 4.110
  3.450 1.650 1.290 4.090 6.320 7.500 3.890 1.580

      5.210
      5.250
      4.930
      7.380
      5.870
      5.810
      9.680
      9.070

      7.290
      7.840
      7.550
      7.320
      7.970
      7.760
      7.000
      8.350

      7.340
      6.350
      6.960
      8.540
      6.620
      4.970
      4.550
      4.810

  4.750 4.760 10.880 10.010 11.620 10.360 6.400 6.240
  7.930 4.040 3.730 5.600 5.350 6.810 8.270 7.680
 6.650 6.080 10.250 9.140 17.750 13.300 9.630 6.800
4.080 5.060 4.940 6.650 7.940 10.760 11.890 5.850
9.010 7.500 10.020 10.380 8.150 8.370 10.730 12.140 : End of time series
```

## 9.3 Program Results

```
G13DMF Example Program Results
```

```
THE MEANS
```

4.370 7.868

CROSS-CORRELATION MATRICES

```
Lag = 1
               0.1,
0.555
        0.736
        0.211
Lag = 2
                0.076
0.260
        0.456
         0.069
Lag = 3
        0.379
                0.014
         0.026
                -0.038
Lag = 4
        0.322
                0.110
        0.093
                -0.236
Lag = 5
        0.341
                0.269
        0.087
                -0.250
Lag = 6
         0.363
                0.344
        0.132
                -0.227
Lag = 7
        0.280
                0.425
         0.207
                -0.128
Lag = 8
        0.248
                0.522
         0.197
                -0.085
Lag = 9
```

0.240

0.254

0.266

0.075

G13DMF.6 [NP3546/20A]

```
Lag = 10
       0.162 -0.020
0.267 0.005
Standard error = 1 / SQRT(N) = 0.144
TABLES OF INDICATOR SYMBOLS
For Lags 1 to 10
Auto-correlation function for series 1
      0.005 : *
+ 0.01 : * * *
0.05 : * * * * *
  Sig. Level
            0.05
                  :
            0.01
            0.005 :
Cross-correlation function for series 1 and series 2
            0.005 :
           Sig. Level
            0.01
            0.01 :
0.005 :
Cross-correlation function for series \ 2 and series \ 1
            0.005 :
           0.01 :
            0.05 :
            0.05 :
                     ----- Lags
  Sig. Level
            0.01
             0.005 :
Auto-correlation function for series 2
           0.005 : *
0.01 : *
0.05 : *
  Sig. Level
                   : - - - - - - - Lags
            0.05
            0.01
            0.005 :
```

[NP3546/20A] G13DMF.7 (last)